

# Adobe<sup>®</sup> FrameMaker<sup>®</sup> 6.0



MML Reference Online Manual



# Contents

<b>Introduction</b>	Using this manual	4
	MML files	4
	Using MML to create FrameMaker documents	5
<b>MML Statements</b>	MML file structure	8
	Markup statement overview	8
	Font statements	11
	Paragraph statements	13
	Document layout statements	16
	Document text statements	17
	Obsolete statement	20
<b>Samples</b>	Specifying document format with a template	21
	Specifying document format with MML	24
<b>MML Messages</b>		
<b>Index</b>		



Adobe, the Adobe logo, Acrobat, Acrobat Reader, Adobe Type Manager, ATM, Display PostScript, Distiller, Exchange, Frame, FrameMaker, FrameViewer, InstantView, and PostScript are trademarks of Adobe Systems Incorporated. Apple, PowerBook, QuickTime, Mac, Macintosh and Power Macintosh are trademarks of Apple Computer, Inc., registered in the United States and other countries. HP-UX is a registered trademark of Hewlett-Packard Company. Microsoft, MS-DOS, Windows, and Windows NT are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries. Sun and Solaris are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and other countries. Unix is a registered trademark and X Window System is a trademark of The Open Group. All other trademarks are property of their respective owners. © 2000 Adobe Systems Incorporated. All rights reserved.

# Introduction

FrameMaker® and FrameMaker+SGML™ include support for a markup language called MML (Maker Markup Language). You can use any standard text editor to create an MML file. Later, you can open the MML file as a FrameMaker document or import it into a FrameMaker template. In a department where different people are responsible for writing and formatting documents, writers can use MML statements to mark up manuals in progress; at the same time, graphic designers can create the formatting specifications in FrameMaker templates.

MML supports many formatting and layout features of FrameMaker documents. For example, you can use MML to specify:

- Document page size, document margins, and number of columns (including the Custom Blank Paper options to the New command)
- Header and footer layouts
- A Paragraph Catalog (including most options available in the Paragraph Designer)
- Font definitions (including most options available in the Character Designer)
- Document text with varying character and paragraph formats (all document text in an MML file is assumed to comprise one text flow)
- Anchored frames containing graphics
- Markers (including all options available in the Marker window)

**MML cannot define the following** (you can add them after you open or import the MML file):

- Unanchored frames and graphics
- Imported text
- Irregular column layouts
- Column layouts that vary from page to page
- Multiple text flows
- Multiple-line or multiple-font headers and footers
- Multiple master pages
- Tables
- Equations
- Side heads
- Stored character formats
- Paragraph, footnote, table, or anchored frames that straddle two or more columns
- Conditional text
- Variables

- Color
- Structure elements
- Text runarounds
- Dashed line patterns

## Using this manual

This manual contains:

- General instructions for creating and using MML files
- A complete description of each MML statement
- Sample MML files
- MML error messages

FrameMaker and FrameMaker+SGML both read MML files. In this manual, the term *FrameMaker* (as in *FrameMaker document* or *FrameMaker product*) refers to either FrameMaker or FrameMaker+SGML. This manual contains information about FrameMaker and FrameMaker+SGML on the UNIX, Macintosh, and Windows platforms.

## MML files

An MML file is a standard ASCII text file containing MML statements and document text. You can create the file with any standard text editor.

After you import or open an MML file, you can modify, print, and save it using FrameMaker document commands. If you open the MML file or import it by copying, any changes you make in the FrameMaker document are not reflected in the original MML file. Thus, if you want the MML file to serve as the master source for the document, you must make the changes to the MML file.

If you import the MML file by reference into a FrameMaker document, you can continue to use the original MML file as the master source for the document. Each time you open the FrameMaker document, it interprets the MML file and updates the resulting text.

If you use your FrameMaker product to create or edit an MML file, save the file as Text Only using the Save As command. To open an MML file as a text file, hold down a modifier key and click Open in the Open dialog box.

On this platform	Use this modifier key
UNIX	Shift
Macintosh	Option
Windows	Control

In FrameMaker products on UNIX, an MML filename must end with the file suffix `.mml`. This suffix alerts your FrameMaker product that the file is an MML file and needs to be interpreted before it is imported into, or opened as, a FrameMaker document.

FrameMaker products on UNIX use the `mmltomif` program to interpret MML files. You can also run `mmltomif` directly to interpret MML files. The `mmltomif` program accepts optional command-line arguments. It has the following syntax:

```
mmltomif -Llanguage -Iinclude_path input_file output_file
```

<code>language</code>	language in use, such as <code>usenglish</code>
<code>include_path</code>	pathname for included files (you can specify multiple include paths by specifying <code>-Iinclude_path</code> for each path you want to search)
<code>input_file</code>	pathname of MML file to read
<code>output_file</code>	pathname of MIF file to write (if you specify this option, you must also specify the <code>input_file</code> option)

FrameMaker products on Macintosh and Windows do not require an `.mml` suffix; the `<MML>` statement identifies a file as an MML file, and a dynamic filter processes the file.

## Using MML to create FrameMaker documents

You can use MML to:

- Specify the content of a document for which formatting information is stored in a FrameMaker template.
- You use a small subset of MML instructions to specify when to use paragraph formats and when to change the character format for words and phrases. You create the paragraph formats and set up the document layout in a FrameMaker template.
- Specify both the content and format of a document.
- You use more complex MML statements to define formatting and layout specifications in the MML file.

When you use MML to create FrameMaker documents, use two MML files to describe a document: an MML *include file* contains formatting information, and an MML *document content file* contains document text. Using two files makes it easier to correct errors. In addition, you can use one include file to create several documents with the same formatting.

If you use a FrameMaker template to specify formatting, your include file can be very brief. It lists the paragraph formats in the template's Paragraph Catalog and any character formats and MML macros you want to use.

If you want to keep formatting information and document content in one file, the file should contain the information that would appear in an include file followed by the information that would appear in a document content file.

## Specifying document format with a FrameMaker template

The easiest way to use MML is to specify formatting information in a FrameMaker template. In addition to the template, you use a simplified include file and a document content file to specify the document text.

For a complete description of the sections in an MML file, see “MML file structure” on page 8. For a sample FrameMaker document created from a template, an include file, and a document content file, see “Specifying document format with a template” on page 21.

### Setting up the template

Open a FrameMaker template, set up the document layout, and create paragraph formats. For information about creating templates, see your user’s manual.

### Creating the include file

Use a standard text editor to create the include file. It should contain:

- An MML identification line
- A Macro Definition section
- A `<!DefineTag>` statement for each paragraph tag in the template (see “Paragraph statements” on page 13)
- Font definitions for character format changes to be used for words or phrases in the document content file

### Creating the MML document content file

Use a standard text editor to create the document content file. It should contain:

- An MML identification line (required)
- An `<Include>` statement that names the MML include file (see “Control and macro statements” on page 10)
- A Document Text section

### Importing the MML file into the template

To create a FrameMaker document from the MML file, use the New command to create a new document from a template. Then use the Import>File command to import the MML document content file into the document. Use the Save As command to save the resulting document under a new filename.

You can also open the MML document content file as a FrameMaker document and use the Import>Formats command from file menu to copy formats from the template into the new document. If you use this method, turn on the option to remove format overrides (see your user’s manual).

## Specifying document format with MML

When you use an include file and a document content file to create a FrameMaker document, the include file describes document formatting; the document content file contains the document text.

For a complete description of the sections in an MML file, see “MML file structure” on page 8. For a sample document created from include and document content files, see “Specifying document format with MML” on page 24.

#### **Creating an include file**

Use a standard text editor to create an include file describing document formatting. It should contain the following sections:

- An MML identification line
- A Macro Definition section
- A Font Definition section
- A Paragraph Format Definition section
- A Document Layout section

#### **Creating a document content file**

Use a text editor to create the document content file. It should contain:

- An MML identification line (required)
- An `<Include>` statement that names the MML include file (see “Control and macro statements” on page 10)
- A Document Text section

#### **Opening the document content file**

To create a FrameMaker document from the include and document content files, open the document content file with your FrameMaker product. When you save the resulting document, a FrameMaker product replaces the `.mml` file suffix with a `.doc` file suffix to avoid overwriting the original MML file.

# MML Statements

An MML file consists of markup statements and document text. Markup statements begin with a left angle bracket (<) and end with a balancing right angle bracket (>). For example, <Section> signals the beginning of a new section, while <Family Times> switches fonts. Case is not significant in statement names, so <FaMiLy Times> would work as well.

All text outside angle brackets is document text. Within document text, adjacent nonblank lines are considered to be in the same paragraph; one or more blank lines separate paragraphs (a blank line is two consecutive return characters). <Paragraph> markup statements can also signal paragraph boundaries. (See “Paragraph statements” on page 13.)

If the text contains a left or right angle bracket character (that is, one that should appear in the FrameMaker document instead of beginning or ending a markup statement), a backslash character must precede the angle bracket (for example, \< or \>).

## MML file structure

An MML file can contain the following sections, in this order.

Section	Contains
MML identification line	An <MML> statement identifying the file as an MML file.
Macro Definition	<!DefineMacro> and <!DefineChar> statements that define simple macros used in subsequent markup statements.
Font Definition	<!DefineFont> statements that define named sets of font properties for use within document text and other markup statements.
Paragraph Format Definition	<!DefinePar> and <!DefineTag> statements that define or declare paragraph formats.
Document Layout	Document layout statements that define document properties.
Document Text	ASCII characters along with font, special character, anchored frame, and paragraph-related markup statements. The first nonspace text character or document text statement outside a markup statement signals the beginning of the document text section.

All sections except the MML identification line and the Document Text section are optional. For information about which sections to include in an MML file, see “Using MML to create FrameMaker documents” on page 5.

## Markup statement overview

The general format of a markup statement is:



`<StatementName OptionalDataItems>`

The following conventions are used to describe the format of data items.

This term	Means
<i>char</i>	A single character code or a backslash equivalent, such as <code>\t</code> for tab (see "MML character set," next).
<i>string</i>	Any sequence of characters enclosed by double quotation marks ("abc"). To use a backslash in a string, type <code>\\</code> . To use double quotation marks in a string, type <code>\"</code> .
<i>commentstring</i>	Any sequence of characters. Double quotation marks are not required.
<i>name</i>	A simple alphanumeric string starting with a nonspace character and ending with a space or a right angle bracket ( <code>&gt;</code> ). Case is not significant.
<i>number</i>	An integer.
<i>boolean</i>	Yes, No, Y, or N. Case is not significant.
<i>measure</i>	A real number, which may contain a decimal point and digits to the right of the decimal point, followed by an optional unit of measurement: <code>inch</code> , <code>in</code> , <code>"</code> (for inch), <code>cm</code> , <code>mm</code> , <code>pica</code> , <code>pc</code> , or <code>pt</code> . If a unit of measurement is not provided, the MML filter uses the default unit (see <code>&lt;Unit&gt;</code> on page 11).
<i>unit</i>	A unit of measurement: <code>inch</code> , <code>in</code> , <code>"</code> (for inch), <code>cm</code> , <code>mm</code> , <code>pica</code> , <code>pc</code> , or <code>pt</code> .
<i>lrcd</i>	Alignment type: <code>left</code> , <code>l</code> , <code>right</code> , <code>r</code> , <code>center</code> , <code>c</code> , <code>leftright</code> , <code>lr</code> , <code>decimal</code> , or <code>d</code> .

### MML character set

MML uses the FrameMaker character set. However, because an MML file can contain only ASCII characters and because of MML parsing requirements, you must represent certain characters in document text with backslash (`\`) sequences.

Character	Representation
Tab	<code>\t</code>
Forced Return	<code>\n</code>
<code>&lt;</code>	<code>\&lt;</code>
<code>&gt;</code>	<code>\&gt;</code>
<code>\</code>	<code>\\</code>
non-ASCII	<code>\xnn</code>

The backslash sequence `\xnn` represents a FrameMaker character code, a 1-digit or 2-digit hexadecimal number that represents a character outside of the printing ASCII range. The backslash sequence must end

with a space. You can use character codes in the ranges \x20 to \x7e and \x80 to \xfe. Other values are ignored. For an explanation of character code values, see the online manual *FrameMaker Character Sets*.

## Control and macro statements

You use control and macro statements to set up your MML file. The following statements (except for the <MML> statement) can appear anywhere in the file.

```
<MML commentstring>
```

All MML files must begin with an <MML> statement.

```
<Comment commentstring>
```

Places comments in the MML file. The *commentstring* argument is ignored when the file is read.

```
<!DefineMacro name string>
```

Replaces all occurrences of the newly defined statement <*name*> with the replacement text in *string*. Note that *string* is rescanned each time *name* is encountered.

*Note: You must put one or more spaces between the name and string arguments when you define a macro.*

For example, suppose your text editor does not give you a way to type the Yen symbol (¥). You can use the following statement to define a new MML statement, <Yen>, that represents the FrameMaker Yen character (\xb4):

```
<!DefineMacro Yen "<Character \\xb4 ">
```

When you import or open your document in a FrameMaker product, MML replaces each <Yen> statement with a Yen character.

For a list of character codes, see the online manual *FrameMaker Character Sets*.

*Note: MML statement names are not case sensitive, so you should not use macro names that are case sensitive.*

For example, suppose you define two macros for the symbols É and é as follows:

```
<!DefineMacro E@' "<Character \\x83 ">
```

```
<!DefineMacro e@' "<Character \\x8e ">
```

When you open this file in a FrameMaker product, MML replaces all <E@'> and <e@'> statements with the symbol é. Because statement names are not case sensitive, MML reads both <!DefineMacro> statements as definitions of the same macro, and it uses the most recently defined macro.

```
<!DefineChar char string>
```

Replaces all occurrences of *char* in the document text with *string*.

*Note: You must put exactly one space between !DefineChar and char and at least one space between char and string.*

Use this statement to remap character codes for foreign and other special keyboards. For example, suppose that the Yen symbol is represented by character code \xfe in the MML file, but the Yen symbol is represented by character code \xb4 in a FrameMaker document. This statement:

```
<!DefineChar \xfe "<Character \\xb4 ">
```

causes MML to convert all `\xfe` characters in the MML file to `\xb4` characters in the FrameMaker document. (See `<Character>` on page 18.)

```
<Include string>
```

Reads the file named *string* as MML input. If you provide just a filename, MML searches for the file in the directory containing the MML file being processed. If you provide a complete pathname, MML searches for the file in the directory specified by the pathname.

```
<Units unit>
```

Establishes default units for all measurements. If a `<Units>` statement appears in the MML file, it must come before the font definitions section. If the statement is not supplied, the default value `inch` is used for all measurements.

```
<!Alias newname currentname>
```

Creates a new statement name that is a synonym for an existing statement name. The *newname* and *currentname* arguments are not enclosed in angle brackets. For example, you could define a synonym and then use the synonym to define a macro as follows:

```
<!Alias !MD !DefineMacro>
```

```
<!MD bi "<Bold><Italic>">
```

You could then use `<bi>` within the document text to set the current font to bold italic.

```
<EndOfInput>
```

Ignores all remaining text in the MML file. Use `<EndOfInput>` to debug an MML file or to temporarily modify an MML file so that a FrameMaker product reads only part of it.

```
<Message string>
```

Prints the specified *string*. Use `<Message>` to debug an MML file.

In FrameMaker products on UNIX, messages appear in the window from which you started your FrameMaker product. In FrameMaker products on Windows and Macintosh, you must turn on Show File Translation Errors in the Preferences dialog box to display messages. The messages appear in a console window in Microsoft Windows and in an Error Log window on the Macintosh.

## Font statements

MML font statements provide character format control similar to the control provided by the Character Designer window or by the Format command in a FrameMaker document. You cannot use MML statements to store character formats in the Character Catalog.

Most of the font statements can appear in the Font Definition, Paragraph Format Definition, Document Layout, and Document Text sections of an MML file. However, `<!DefineFont>` can appear only in the Font Definition section.

```
<family name>
```

Changes font family. The *name* argument must match a font family name that is installed with a FrameMaker product; case is significant. The font families are listed in the Format>Font submenu. If no `<family>` statement is provided, the default family is `Times`.

```

<italic>
<noitalic>
<bold>
<nobold>
<underline>
<nounderline>
<strike>
<nostrike>
<oblique>
<nooblique>

```

These statements turn various font styles on and off. A font style remains in effect until you turn it off. For example, the following MML input:

```
You can switch from <bold> bold to <nobold> plain font styles.
```

produces this result in a FrameMaker document:

You can switch from **bold** to plain font styles.

The `<italic>` and `<oblique>` statements are synonymous, as are the `<noitalic>` and `<nooblique>` statements.

```
<plain>
```

Same as `<nobold>` `<noitalic>` `<nounderline>` `<nostrike>`. The default style is `<plain>`.

```
<superscript>
```

```
<subscript>
```

```
<normal>
```

These statements change the relative position of the text baseline. The baseline position remains in effect until you turn it off. The default position is `<normal>`.

For example, the following MML input:

```
e<superscript>i*pi<normal>=-1
```

produces this result in a FrameMaker document:

$e^{i\pi}=-1$

```
<pts number>
```

Changes font size. For example, `<pts 10>` changes the current font size to 10 points. The default size is `<pts 12>`.

```
<!DefineFont name fontstatements>
```

Defines a character format. It executes the list of *fontstatements* (the statements defined in this section) and then establishes the current font properties as the character format. For examples of `<!DefineFont>` and its use, see “Samples” on page 21.

The character formats you define in an MML file are used to indicate font changes for words and phrases. However, they do not correspond to the formats stored in a document’s Character Catalog, so you cannot

store formats in the Character Catalog or apply a character format by using the tags of formats stored in the Character Catalog.

## Paragraph statements

Paragraph statements in MML provide a subset of the paragraph formatting control provided by the Paragraph Designer.

Most paragraph statements can appear within the Paragraph Format Definition section and between paragraphs in the Document Text section. Exceptions are `<!DefinePar>` and `<!DefineTag>`, which can appear only in the Paragraph Format Definition section.

`<par>`

Ends a paragraph. The current font properties and paragraph settings remain in effect. Two or more consecutive return characters act as a `<par>` statement. A new paragraph begins only when a nonspace text character is read; leading tabs and spaces are ignored. To begin a paragraph with a tab, use the predefined `<Tab>` macro (see `<Character>` on page 18). To begin a paragraph with a space, use the predefined `<HardSpace>` macro or define your own `<Space>` macro by using the `<!DefineMacro>` statement (see `<!DefineMacro>` on page 10). The `<par>` statement is most useful within macro definitions.

`<LeftIndent measure>`

Changes the paragraph left indent. The default value is 0".

`<RightIndent measure>`

Changes the paragraph right indent. The default value is 0".

`<FirstIndent measure>`

Sets the left indent for the first line of a paragraph. The default value is 0".

`<SpaceBefore measure>`

Sets the space above the paragraph. The default value is 0pt.

`<SpaceAfter measure>`

Sets the space below the paragraph. The default value is 0pt.

`<Leading measure>`

Determines the space between lines within the paragraph. The default value is 2pt.

*Note: Always specify a unit in a `measure` argument. If you don't, MML uses the current default unit, which is set by the `<Units>` statement and is usually inches. So `<Leading 2>` would put 2 inches of leading between each paragraph, not 2 points.*

`<Alignment lrc>`

Sets the alignment of paragraph lines. The default value is `lr` (justified).

`<AutoNumber boolean>`

Sets automatic numbering of paragraphs. If `<AutoNumber Yes>` is specified, there must also be a valid `<NumberFormat>` string. The default value is `No` (no automatic numbering).

`<NumberFormat string>`

Determines the numbering format for paragraphs that are automatically numbered. Ignored unless `<AutoNumber Yes>` is specified. The default value is "" (an empty string).

A paragraph autonumber format in an MML file can contain a number series label, printing characters, and counters. However, MML supports a limited form of autonumbering. To use the full functionality of autonumbering in a FrameMaker document, set up the autonumber format in a FrameMaker template rather than in an MML file (see your user's manual).

To specify an autonumber format in the MML file, specify an optional series label, a counter, and printing characters. Use the following syntax for counters.

Use	To
A plus sign (+)	Increase the value of the counter by 1
A number sign (#)	Use the current value of the counter
A number	Set the value of the counter to the specified number

For example, the following table shows three autonumber formats for section, subsection, and sub-subsection headings.

This autonumber format	Appears in the document as	
<code>&lt;NumberFormat "Section +.0\t"&gt;</code>	Section 1.0	Section heading
<code>&lt;NumberFormat "Section +.0\t"&gt;</code>	Section 2.0	Next section heading
<code>&lt;NumberFormat "Section #.+ \t"&gt;</code>	Section 2.1	Subsection heading
<code>&lt;NumberFormat "Section #.+ \t"&gt;</code>	Section 2.2	Next subsection heading
<code>&lt;NumberFormat "Section #.#.+ \t"&gt;</code>	Section 2.2.1	Sub-subsection heading
<code>&lt;NumberFormat "Section #.#.+ \t"&gt;</code>	Section 2.2.2	Next sub-subsection heading
<code>&lt;NumberFormat "Section +.0\t"&gt;</code>	Section 3.0	Next section heading

`<Hyphenate boolean>`

Turns automatic hyphenation on or off. The default value is `Yes` (automatic hyphenation).

`<ColumnTop boolean>`

Sets the starting place for the paragraph on the page. If `<ColumnTop Yes>` is specified, the paragraph starts at the top of a column; otherwise it starts anywhere. These settings correspond to the Start Anywhere and Start Top of Column properties in the Paragraph Designer. The default value is `No` (paragraph starts anywhere).

`<WithNext boolean>`

Determines whether or not to keep the paragraph in the same column as the beginning of the next paragraph. The default value is `No` (don't keep paragraphs together).

`<Tolerance number>`

Specifies the maximum number of adjacent lines that may be hyphenated when automatic hyphenation is turned on. The default value is 2.

```
<BlockSize number>
```

Specifies the minimum number of widow and orphan lines. The default value is 1.

```
<TabStop dimension>
```

Sets a tab stop at the indicated position. This statement can only appear in a <TabStops> statement.

```
<TabStopType lrcd>
```

Establishes the tab type for all subsequently defined tab stops until the next <TabStopType> statement. This statement can only appear in a <TabStops> statement. The default value is 1 (left tab).

```
<TabStopLeader char>
```

Establishes the tab leader character for all subsequently defined tab stops until the next <TabStopLeader> statement. This statement can only appear in a <TabStops> statement. The default value is the space character (no leader).

*Note: You must have exactly one space between TabStopLeader and the char argument when you define a tab stop leader.*

```
<TabStops tabstatements>
```

Defines a set of tab stops. Each tab stop is determined by a <TabStop> substatement. The tab type and associated leader character are determined by the most recent <TabStopType> and <TabStopLeader> substatements, which may be freely intermingled among the <TabStop> substatements, as shown in the following example:

```
<TabStops
  <TabStopType 1>
  <TabStopLeader .>
  <TabStop .5">
>
```

To clear all tabs, use an empty tab stop list: <TabStops>.

```
<!DefinePar name parstatements>
```

Creates a named paragraph format that has the paragraph properties specified in the list of *parstatements* (the statements defined in this section, “Paragraph statements”).

When you open or import an MML document, the resulting FrameMaker document contains a Paragraph Catalog entry for each paragraph format defined in the MML file using <!DefinePar> statements. A stored paragraph format is applied to any MML paragraph that is preceded by the format’s tag. For examples of the <!DefinePar> statement and its use, see “Include file” on page 24.

```
<!DefineTag name>
```

Establishes a paragraph format name like <!DefinePar>. However, unlike <!DefinePar>, <!DefineTag> does not generate a Paragraph Catalog entry when the MML file is imported or opened as a FrameMaker document.

Use <!DefineTag> when you want to import an MML file into a FrameMaker document that already has the Paragraph Catalog set up or when you will import formats from a template. When an MML paragraph

is preceded by a tag declared by a `<!DefineTag>` statement, the FrameMaker document's Paragraph Catalog is searched for a format with a matching tag. If such a format exists, the paragraph's format is set to match the corresponding format in the Paragraph Catalog. For examples of the `<!DefineTag>` statement and its use, see "Include file" on page 22.

*Note: MML tag names cannot have a space in them (although tag names in a FrameMaker document can). The name argument must match a tag name in the Paragraph Catalog; case is significant.*

## Document layout statements

MML's document layout statements provide control similar to the control provided by the Custom Blank Paper options to the New command and by the Column Layout and Page Size commands. (See your user's manual.)

Document layout statements may appear only in the document layout section.

`<PageWidth measure>`

Sets the page width. The default value is 8.5".

`<PageHeight measure>`

Sets the page height. The default value is 11".

`<TopMargin measure>`

`<BottomMargin measure>`

`<LeftMargin measure>`

`<RightMargin measure>`

Sets the page's top, bottom, left, and right margins. Each margin is offset from the corresponding edge of the paper and defines the area occupied by a text frame. The default value for each margin is 1".

`<Columns number>`

Sets the number of columns. The default value is 1.

`<ColumnGap measure>`

Determines the gap between columns. The default value is 0.25".

`<LeftHeader string>`

`<CenterHeader string>`

`<RightHeader string>`

`<LeftFooter string>`

`<CenterFooter string>`

`<RightFooter string>`

Establishes the specified *string* as part of a page header or page footer (left-aligned, centered, or right-aligned). The default value is "" (an empty string).

To insert a page number variable in a header or footer, use a number sign (#) in the string.

`<HeaderFont fontstatements>`



Designates the specified font statements or a named font definition to be used in all header and footer strings. The default value is `<Family Times> <pts 12> <Plain>`.

`<HeaderTopMargin measure>`

Specifies the margin from the top edge of the paper to the header. The header sits just below the margin. The default value is 0.5".

`<HeaderBottomMargin measure>`

Specifies the margin from the bottom edge of the paper to the baseline of the footer. The default value is 0.5".

`<HeaderLeftMargin measure>`

Specifies the margin from the left edge of the paper to the header and footer. The default value is 1".

`<HeaderRightMargin measure>`

Specifies the margin from the right edge of the paper to the header and footer. The default value is 1".

`<HeaderPageNumberStyle style>`

Specifies the document's main page numbering style where *style* is `Arabic`, `UCRoman`, `LCRoman`, `UCAAlpha`, or `LCAAlpha`. The default value is `Arabic`.

`<FirstPageHeader boolean>`

Controls whether or not headers are displayed on the first page of a document. The default value is `Yes` (display headers).

`<FirstPageFooter boolean>`

Controls whether or not footers are displayed on the first page of a document. The default value is `Yes` (display footers).

`<DoubleSided boolean>`

Specifies single-sided or double-sided pagination. `No` means single-sided. The default value is `No`.

`<FirstPageLeft boolean>`

Specifies a left or right first page. `No` means the first page is considered a right page. `<FirstPageLeft>` is meaningful only if preceded by a `<DoubleSided Yes>` statement. The default value is `No` (first page is a right page).

`<FirstPageNumber number>`

Sets the number for the first page of the document. The default value is 1.

## Document text statements

The Document Text section contains:

- Text outside of markup statements
- Font statements and references to named character formats (see `<!DefineFont>` on page 12)
- Paragraph statements and references to named paragraph formats (see `<!DefinePar>` on page 15 and `<!DefineTag>` on page 15)

- Macros defined with `<!DefineMacro>` and `<!DefineChar>` (see “Control and macro statements” on page 10)
- `<Character>` statements (described in this section)
- Anchored frames defined with `<AFrame>` statements (described in this section)
- Markers defined with `<Marker>` statements (described in this section)

Regular document text in an MML file can only contain ASCII characters. To include special characters in regular document text, use a backslash sequence (see “MML character set” on page 9) or use the `<Character>` statement (described next).

`<Character number>`

Represents a character code value in the ranges 32 to 126 and 128 to 254 (`\x20` to `\x7e` and `\x80` to `\xfe`). Other values are ignored. To use hexadecimal values in a `<Character>` statement, leave a space between the number and the right bracket (for example, `<Character \x86 >`). Use `<Character>` statements to enter characters outside the printing ASCII range. They may occur within document text and within definitions of macros that are used in document text. Whenever `<Character>` statements are nested within `<!DefineMacro>` and `<!DefineChar>` statements, you must type two backslashes before the hexadecimal value. For example:

```
<!DefineChar \xfe "<Character \\xb4 >" >
```

Two backslashes are necessary because of the order in which the MML filter processes the statement. Note that `!DefineChar` must be followed by exactly one space.

You can also use the following predefined macros, which expand to the appropriate `<Character>` statements.

Macro name	Description
<code>&lt;Tab&gt;</code>	Tab
<code>&lt;HardSpace&gt;</code>	Nonbreaking space
<code>&lt;DiscHyphen&gt;</code>	Discretionary hyphen
<code>&lt;NoHyphen&gt;</code>	Suppress hyphenation
<code>&lt;Cent&gt;</code>	Cent (¢)
<code>&lt;Pound&gt;</code>	Sterling (£)
<code>&lt;Yen&gt;</code>	Yen (¥)
<code>&lt;EnDash&gt;</code>	En dash (–)
<code>&lt;EmDash&gt;</code>	Em dash (—)
<code>&lt;Dagger&gt;</code>	Dagger (†)
<code>&lt;DoubleDagger&gt;</code>	Double dagger (‡)
<code>&lt;Bullet&gt;</code>	Bullet (•)
<code>&lt;HardReturn&gt;</code>	Forced return

```
<AFrame <BRect l t w h>>
```

Creates an anchored frame, placing the anchor symbol after the character that precedes the <AFrame> statement. The <AFrame> statement must contain a <BRect> statement that gives the frame's left and top coordinates relative to the enclosing page or frame and the frame's width and height. Following the <BRect> statement, there may be other substatements, including the <FrameType> statement (used to define the frame's position relative to the anchor symbol). The <AFrame> statement, and all its substatements, are MIF (Maker Interchange Format) statements. For information about MIF statements, see the online manual *MIF Reference*.

A minimal <AFrame> statement is:

```
<AFrame <BRect 0 0 4" 2"> >
```

This statement places an empty 4-inch by 2-inch anchored frame in the document. The default frame type is <FrameType Below>, which corresponds to the Below Current Line setting in the Anchored Frame dialog box. (See your user's manual.)

For an example of an <AFrame> statement that includes graphics, see "Document content file" on page 26.

```
<Marker MarkerSubstatements>
```

Inserts a marker. You can use the following MIF <Marker> substatements to describe the marker's settings; other MIF <Marker> substatements are not allowed.

Statement	Marker setting
<MType <i>number</i> >	Specifies the marker type number. The marker type numbers correspond to the marker names in the Marker window as follows:
	0 Header/Footer \$1
	1 Header/Footer \$2
	2 Index
	3 Comment
	4 Subject
	5 Author
	6 Glossary
	7 Equation
	8 Hypertext
	9 Cross-Ref
	10 Conditional Text
	11 through 25 Type 11 through Type 25
<MText <i>string</i> >	Specifies the marker text. The string must begin with a left single quotation mark (') and end with a straight single quotation mark ('). You cannot use double quotation marks (").

For example:

```
<Marker <MType 2> <MText `rectangles, drawing'> >
```

describes an index entry with the text “rectangles, drawing.”

To include a left angle bracket (<), right angle bracket (>), or backslash (\) in the marker text, precede it with a backslash. For example:

```
<Marker <MType 2>  
  <MText `duplicate, see copy\<$nopage\>'>  
>
```

describes an index marker whose marker text is “duplicate, see copy<\$nopage>”.

For more information about MIF <Marker> substatements, see the online manual *MIF Reference*.

## Obsolete statement

The following MML statement is obsolete:

```
<ForceFont>
```

MML reads a <ForceFont> statement but ignores it.

# Samples

This appendix contains sample MML descriptions of documents. The sample documents have been provided with this manual and are located in the directory or folder in which your FrameMaker product is installed.


For a FrameMaker product on this platform	Look here
UNIX	The <code>/fminit/language/Samples</code> directory, where <i>language</i> is the language in use, such as <code>usenglish</code>
Macintosh	The <code>Samples</code> folder
Windows	The <code>samples</code> directory

The MML sample files have the file suffix `.mml`.

## Specifying document format with a template

The following illustration shows a document created by importing an MML file into the standard FrameMaker template `Book/Chapter` (`book/chapter` in Windows).

To create this sample document, use the New command to create a new document from the Book/Chapter template. Then use the Import>File command to import the MML sample file `chaptxt.mml` into the document.



## Include file

The following include file, `chapfmt.mml`, contains `<!DefineTag>` statements for paragraph formats in the Chapter template.

```
<MML>
<Comment *** Include file for Chapter template>
<Comment *** Define paragraph formats in the Book/Chapter template>
<!DefineTag Body>
<!DefineTag BodyAfterHead>
<!DefineTag Bulleted>
<!DefineTag BulletedCont>
<!DefineTag CellBody>
<!DefineTag CellHeading>
<!DefineTag ChapterTitle>
```

```

<!DefineTag Equation>
<!DefineTag Extract>
<!DefineTag Figure>
<!DefineTag Footnote>
<!DefineTag Heading1>
<!DefineTag Heading2>
<!DefineTag HeadingRunin>
<!DefineTag Numbered>
<!DefineTag Numbered1>
<!DefineTag NumberedCont>
<!DefineTag TableFootnote>
<!DefineTag TableTitle>

```

## Document content file

The following file, `chaptxt.mml`, contains the chapter text; each paragraph is tagged with one of the formats defined in the include file.

```

<MML>
<Comment *** Include formats in chapfmt.mml>
<Include "chapfmt.mml">
<Comment *** Report Body>
<ChapterTitle>
<Marker <MType 2> <MText `volcanic eruptions\<$startrange\>'> >Study of Volcanic
Eruptions
<BodyAfterHead>
Volcanology, a branch of geology, is the study of volcanoes and volcanic
activity. Although volcanoes are difficult to study because of the hazards
involved, volcano observatories have existed for decades.
<Heading1>
Types of eruptions
<BodyAfterHead>
Volcanoes erupt in a wide variety of ways. Even a single volcano may go through
several eruption phases in one active period. Eruptions are classified according
to the geochemical composition and viscosity of the lavas, nature of the flows
or ash release, and associated phenomena. Magmatic eruptions are the most
common, but the most violent arise from steam explosions when the fiery magma
reaches surface water, ice, or groundwater.
<Heading2>
<Marker <MType 2> <MText `eruptions, Pelean'> >Pelean eruptions
<BodyAfterHead>
Pelean eruptions, named after the 1902 eruption of Mount Pelee on the Caribbean
island of Martinique, are characterized by incandescent flows of rock and pumice
fragments. The entrapment of high-temperature gases in these `glowing
avalanches,' known by the French term <italic>nuee ardente</noitalic>, is
associated with a particularly violent phase of eruption.
<Marker <MType 2> <MText `volcanic eruptions\<$endrange\>'> >

```


## Specifying document format with MML

The following illustration shows a document created from two MML files:

- An include file contains document formats.
- A document content file contains the document text.

The two files can be merged; however, you should keep format information and document content in separate files.

To create this sample document, open the MML file `sample.mml`.



### Include file

The following include file, `formats.mml`, contains formatting information.

```
<MML 1.00 - Sample standard font, paragraph, and document formats>
```

```
<Comment *** Define fonts for Title, Section, Body, Headers and Footers. Most of the defaults are good, so we just specify family, size, and style. "ft" stands for "font for Titles", "fs" is "font for sections," etc.>
```



```
<!DefineFont ft
  <Family Times>
  <pts 18>
  <Bold>
>
<!DefineFont fs
  <Family Times>
  <pts 14>
  <Bold>
>
<!DefineFont fb
  <Family Times>
  <pts 12>
  <Plain>
>
<!DefineFont fhf
  <Family Times>
  <pts 10>
  <Plain >
>
<Comment *** Set appropriate font for a Title paragraph and define its format.>
<!DefinePar Title
  <ft>
  <Alignment Center>
  <SpaceAfter 12pt>
>
<Comment *** Set font and define other paragraph formats.>
<!DefinePar Section
  <fs>
  <Alignment Left >
  <LeftIndent 0.50">
  <FirstIndent 0.00">
  <RightIndent 0.00">
  <Leading 0pt>
  <SpaceBefore 9pt>
  <SpaceAfter 9pt>
  <AutoNumber Yes >
  <NumberFormat "+.0\t">
  <TabStops <TabStop 0.50"> >
>
```

```
<!DefinePar Body
  <fb>
  <Alignment LeftRight >
  <LeftIndent 0.50">
  <FirstIndent 0.50">
  <RightIndent 0.00">
  <Leading 2pt>
  <SpaceBefore 0pt>
  <SpaceAfter 10pt>
  <AutoNumber No >
  <TabStops>
>
<!DefinePar BulletItem
  <Alignment Left >
  <LeftIndent 0.75">
  <FirstIndent 0.50">
  <RightIndent 0.00">
  <Leading 2pt>
  <SpaceBefore 0pt>
  <SpaceAfter 3pt>
  <AutoNumber Yes>
  <NumberFormat "\xA5 \t">
  <Comment *** \xA5 is the bullet character. \t is a tab character.>
  <TabStops <TabStop 0.75">>
>
<Comment *** Document Layout descriptions. Most of the default settings are
good. >
<Pagewidth 7.00">
<PageHeight 10.00">
<TopMargin 0.75">
<BottomMargin 0.75">
<LeftMargin 0.50">
<RightMargin 0.50">
<HeaderTopMargin 0.40">
<HeaderBottomMargin 0.46">
<HeaderLeftMargin 1.00">
<HeaderRightMargin 1.00">
```

### Document content file

The following MML file, `sample.mml`, contains the document text.

```
<MML 1.00 A sample mml file>
```

```
<Comment *** Include the font, paragraph, document definitions from another  
file. By keeping the formats in different files than the document text, all  
documents can be assigned a new format by just changing one file.>
```

```
<Comment *** Include formats in formats.mml>
```

```
<Include "formats.mml">
```

```
<Comment *** Define a few macros just to show how it is done. Would normally put  
such standard macros in an include file.>
```

```
<!DefineMacro if "<Italic>">
```

```
<!DefineMacro pf "<Plain>" >
```

```
<!DefineMacro bf "<Bold>" >
```

```
<Comment *** Set up Headers and Footers. The next line sets the font.>
```

```
<HeaderFont <fhf>>
```

```
<RightHeader "Maker Markup Language Specification">
```

```
<LeftFooter "Second Draft">
```

```
<RightFooter "Page #">
```

```
<Comment *** Start of Document Text ***>
```

```
<Title>
```

```
Maker Markup Language Specification
```

```
<Section>
```

```
Introduction
```

```
<Body>
```

```
Maker Markup Language (MML) is used to create formatted FrameMaker documents  
from a text file. MML allows access to many FrameMaker product features.
```

```
<Comment *** The following Body paragraph contains an anchored frame. The AFrame  
statement is equivalent to a MIF AFrame statement. (For a detailed description,  
see the online manual "MIF Reference.") Inside the frame is a star. We just  
show this here so you can see how it is done.>
```

```
MML allows formatted documents to be created using both a <if>GENCODE <pf>style  
of markup, in which document format and content are separate notions,
```

```
<AFrame <BRect 0 0 4 2> <FrameType Below>
```

```
<Polygon
```

```
<Pen 0> <PenWidth `1.0'> <Fill 6> <Inverted No >
```

```
<NumPoints 10>
```

```
<Point 2.03" 0.29"> <Point 2.19" 0.83"> <Point 2.76" 0.83">
```

```
<Point 2.28" 1.17"> <Point 2.49" 1.71"> <Point 2.03" 1.36">
```

```
<Point 1.56" 1.71"> <Point 1.76" 1.15"> <Point 1.28" 0.83">  
<Point 1.86" 0.83">  
> # end of Polygon  
>
```

and a formatting style of markup, in which actual formatting specifications are intermingled with the document text.

This document contains the following sections:

<BulletItem>

Instructions for creating MML documents

Overview of MML file format and syntax

Description of each MML Statement

Sample MML file

<Section>

Creating and Using MML Documents

<Body>

An MML document is a text file containing MML statements, text broken up into paragraphs. It can be created using any text editor. It can also be created using a FrameMaker product: when saving the document, specify Text Only in the Save dialog box.

<Comment \*\*\* Would be followed by additional such lines>

# MML Messages

FrameMaker products use an MML filter to read an MML file. The filter translates the MML file and produces a temporary MIF file that a FrameMaker product opens as a document. While the filter is reading the MML file, it might detect errors such as unexpected character sequences. It responds by displaying error messages. Even if it finds an error, the filter continues to process the MML file and reads as much of the document as possible.

This section lists the messages produced by the filter, along with their explanations. Words in *italic* indicate variable words in a message. A line number is printed along with most messages when they appear on the screen.

**MML MSG:** *Message\_String*.

Not an error; generated by a user `<Message>` statement.

**MML:** **Bad option** *'Character'*.

The filter did not recognize this option character. The option is ignored.

**Bad Boolean:** *'Unexpected\_String'*.

The filter expected to see `Yes` or `No`. The value `No` is assumed.

**Bad lrcd:** *'Unexpected\_String'*.

The filter expected to see `Left`, `Right`, `Center`, `Decimal`, or `LeftRight`.

**Bad real number:** *'Unexpected\_Char'*.

A nonreal number character appeared in the middle of a real number.

**Bad style:** *'Unexpected\_String'*.

The filter expected to see `Arabic`, `LCRoman`, `UCRoman`, `LCAlpha`, or `UCAlpha`.

**Bad unit:** *'Unexpected\_String'*.

The filter expected to see a valid unit (`inch`, `cm`, and so on).

**Cannot find** *'filename'*.

The filter can't find the specified input file. Make sure that the file exists, and that you have read access to it; then try again.

**Cannot find end of comment on line** *n*.

The comment that began on the specified line did not end by the time the file was completely read.

**Cannot open *filename*.**

The filter couldn't find the named include file. Make sure that the file is in the correct format and that you have read access to it; then try again. If this message still appears, close some open files or windows and try again.

**Cannot open temporary file.**

The filter couldn't open its temporary file. Make sure you have write access to `/tmp`, your home directory, or the current directory; then try again. If this message still appears, close some open files or windows and try again.

**Cannot write *filename*.**

The filter couldn't open the specified output file for writing. Make sure you have write access; then try again. If this message still appears, close some open files or windows and try again.

**Character '*Character*' needs ending space.**

Characters specified with `\x` must end with a space.

**Expected string, not '*Unexpected\_Char*'.**

The filter expected to see a string starting with a double quotation mark (") rather than the unexpected character shown in the message.

**FATAL!**

The filter encountered a problem from which it can't recover. Write down the error message and contact Adobe Technical Support.

**Input stack overflow.**

There are too many nested include files (maybe in an include loop). The maximum nesting depth is 100.

**Internal Error.**

The filter encountered an internal error. Please contact Adobe Technical Support.

**Junk at end of command: *Junk\_String*.**

The filter expected to see a right angle bracket (>).

**Keyword too long: over 1000 characters.**

While looking for a macro name or other keyword, the filter found a very long token (over 1,000 characters). Check the MML file for a syntax error and try again.

**Never finished defining '*Character*'.**

The filter encountered a `<!Define...>` statement within a `<!Define...>` statement (for example, a `<!DefineChar>` statement within a `<!DefinePar>` statement). You must finish the first `<!Define...>` statement before beginning another.

The filter ignores the first `<!Define...>` statement and continues reading the file. The results, however, are not likely to be what you intended.

**Out of memory!**

The filter was unable to complete the translation of the MML file because it ran out of memory. To free memory for the filter, quit some FrameMaker document windows or terminate other processes.

**String too long.**

A very long string was found. The maximum string length is 1000 characters; characters beyond that are truncated.

**Tab commands allowed only within** `<TabStops . . .>`.

The statements `<TabStopType>`, `<TabStopLeader>`, and `<TabStop>` can appear only within a `<TabStops>` statement.

**Too many -I options.**

The maximum number of `-I` options is 100. The `mmltomif` filter exits. (This error message is valid only for FrameMaker products on UNIX.)

**Undefined macro:** *Macro\_Name*.

There is no definition for this macro. The undefined macro is ignored.

**Unexpected right angle bracket.**

A right angle bracket (`>`) with no matching left bracket (`<`) has appeared.

**Usage:** `mmltomif [-L language] [-I path] [input [output]]`.

You started `mmltomif` in a shell window with incorrect parameters. Restart `mmltomif` with the following parameters:

<i>language</i>	language in use, such as <code>usenglish</code>
<i>path</i>	pathname for included files (you can specify multiple include paths by specifying <code>-I path</code> for each path you want to search)
<i>input</i>	pathname of MML file to read
<i>output</i>	pathname of MIF file to write (if you specify this option, you must also specify the <i>input</i> option)

This error message is valid only for FrameMaker products on UNIX.

# Index

## Symbols

!Alias statement 11  
 !DefineChar statement 10  
 !DefineFont statement 12  
 !DefineMacro statement 10  
 !DefinePar statement 15  
 !DefineTag statement 15  
 < (left angle bracket) 8  
 > (right angle bracket) 8  
 \ (backslash), using for special characters 9

## A

AFrame statement 19  
 !Alias statement 11  
 Alignment statement 13  
 angle brackets (< >) 8  
 AutoNumber statement 13

## B

backslash (\), using for special characters 9  
 BlockSize statement 15  
 bold statement 12  
 BottomMargin statement 16  
 BRect statement 19

## C

CenterFooter statement 16  
 CenterHeader statement 16  
 chapfmt.mml file 22  
 chaptxt.mml file 23  
 character codes, using for special characters 9, 18  
 character formats, defining 12  
 Character statement 18  
 characters, defining 10, 18  
 ColumnGap statement 16  
 Columns statement 16  
 ColumnTop statement 14  
 Comment statement 10  
 control statements 10–11

conventions, notation 9

## D

data item conventions 9  
 !DefineChar statement 10  
 !DefineFont statement 12  
 !DefineMacro statement 10  
 !DefinePar statement 15  
 !DefineTag statement 15  
 document content files 5  
   creating 6, 7  
   sample 23, 26  
 document format  
   specifying with a FrameMaker template 6  
   specifying with MML 6  
 document layout statements 16–17  
 document text statements 17–20  
 DoubleSided statement 17

## E

EndOfInput statement 11  
 error messages 29–31

## F

family statement 11  
 file identifier 10  
 files, including 11  
 FirstIndent statement 13  
 FirstPageFooter statement 17  
 FirstPageHeader statement 17  
 FirstPageLeft statement 17  
 FirstPageNumber statement 17  
 font  
   family, specifying 11  
   for headers and footers, specifying 16  
   format, defining 12  
   size, specifying 12  
   statements 11–13  
   styles, specifying 12  
 footer margins, specifying 17

footers, specifying 16  
 formats.mml file 24

## G

gap between columns, specifying 16

## H

header margins, specifying 17  
 HeaderBottomMargin statement 17  
 HeaderFont statement 16  
 HeaderLeftMargin statement 17  
 HeaderPageNumberStyle statement 17  
 HeaderRightMargin statement 17  
 headers, specifying 16  
 HeaderTopMargin statement 17  
 Hyphenate statement 14

## I

include files 5  
   creating 6, 7  
   sample 22, 24  
   search path 11  
 Include statement 11  
 indents, specifying 13  
 italic statement 12

## L

Leading statement 13  
 LeftFooter statement 16  
 LeftHeader statement 16  
 LeftIndent statement 13  
 LeftMargin statement 16

## M

macro statements 10–11  
 macros  
   defining 10  
   predefined 18  
 margins, specifying page 16  
 Marker statement 19  
 markup statements 8–20



- format 8
  - Message statement 11
  - messages 29–31
  - MML files 4
    - creating 4
    - file identifier 10
    - filename suffix 5
    - samples 21–28
    - structure 8
  - MML messages 29–31
  - MML statement 10
  - MText statement 19
  - MType statement 19
- N**
- nobold statement 12
  - noitalic statement 12
  - nooblique statement 12
  - normal statement 12
  - nostrike statement 12
  - notation, conventions 9
  - nounderline statement 12
  - NumberFormat statement 13
- O**
- oblique statement 12
  - orphan line control 15
  - overstrike font style 12
- P**
- page headers and footers, specifying 16
  - page margins
    - for body text 16
    - for header and footer 17
  - page numbering 17
  - PageHeight statement 16
  - PageWidth statement 16
  - par statement 13
  - paragraph format, defining 15
  - paragraph statements 13–16
  - paragraph tag, defining 15
  - paragraph, ending 13
  - pathnames, for included files 11
  - plain statement 12
  - pts statement 12
- R**
- RightFooter statement 16
  - RightHeader statement 16
  - RightIndent statement 13
  - RightMargin statement 16
- S**
- sample.mml file 26
  - search path, for included files 11
  - space between lines, specifying 13
  - SpaceAfter statement 13
  - SpaceBefore statement 13
  - spaces, in paragraph tags 16
  - special characters 9, 18
    - predefined 18
  - statements
    - control 10–11
    - document layout 16–17
    - document text 17–20
    - font 11–13
    - macro 10–11
    - paragraph 13–16
  - strike statement 12
  - strikethrough font style 12
  - subscript statement 12
  - superscript statement 12
- T**
- TabStop statement 15
  - TabStopLeader statement 15
  - TabStops statement 15
  - TabStopType statement 15
  - Tolerance statement 14
  - TopMargin statement 16
- U**
- underline statement 12
  - Units statement 11
- W**
- widow line control 15
  - WithNext statement 14