

ADOBE® FRAMEMAKER® 9

STRUCTURED APPLICATION DEVELOPER REFERENCE

© 2009 Adobe Systems Incorporated and its licensors. All rights reserved.

Structured Application Developer Reference Online Manual

If this guide is distributed with software that includes an end-user agreement, this guide, as well as the software described in it, is furnished under license and may be used or copied only in accordance with the terms of such license. Except as permitted by any such license, no part of this guide may be reproduced, stored in a retrieval system, or transmitted, in any form or by any means, electronic, mechanical, recording, or otherwise, without the prior written permission of Adobe Systems Incorporated. Please note that the content in this guide is protected under copyright law even if it is not distributed with software that includes an end-user license agreement.

The content of this guide is furnished for informational use only, is subject to change without notice, and should not be construed as a commitment by Adobe Systems Incorporated. Adobe Systems Incorporated assumes no responsibility or liability for any errors or inaccuracies that may appear in the informational content contained in this guide.

Please remember that existing artwork or images that you may want to include in your project may be protected under copyright law. The unauthorized incorporation of such material into your new work could be a violation of the rights of the copyright owner. Please be sure to obtain any permission required from the copyright owner.

Any references to company names in sample templates are for demonstration purposes only and are not intended to refer to any actual organization.

Adobe, the Adobe logo, Acrobat, Distiller, Flash, FrameMaker, Illustrator, PageMaker, Photoshop, PostScript, Reader, Garamond, Kozuka Mincho, Kozuka Gothic, MinionPro, and MyriadPro are trademarks of Adobe Systems Incorporated.

Microsoft, Windows, and Windows Vista are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries. Solaris is a trademark or registered trademark of Sun Microsystems, Inc. in the United States and other countries. UNIX is a trademark in the United States and other countries, licensed exclusively through X/Open Company, Ltd. SVG is a trademark of the World Wide Web Consortium; marks of the W3C are registered and held by its host institutions MIT, INRIA, and Keio. All other trademarks are the property of their respective owners.

This product contains either BISAPE and/or TIPEM software by RSA Data Security, Inc.

This product contains color data and/or the Licensed Trademark of The Focoltone Colour System.

PANTONE® Colors displayed in the software application or in the user documentation may not match PANTONE-identified standards. Consult current PANTONE Color Publications for accurate color. PANTONE® and other Pantone, Inc. trademarks are property of Pantone, Inc. © Pantone, Inc. 2003. Pantone, Inc. is the copyright owner of color data and/or software which are licensed to Adobe Systems Incorporated to distribute for use only in combination with Adobe Illustrator. PANTONE Color Data and/or Software shall not be copied onto another disk or into memory unless as part of the execution of Adobe Illustrator software.

Software is produced under Dainippon Ink and Chemicals Inc.'s copyrights of color-data-base derived from Sample Books.

This product contains ImageStream® Graphics and Presentation Filters Copyright ©1991-1996 Inso Corporation and/or Outside In® Viewer Technology ©1992-1996 Inso Corporation. All Rights Reserved.

This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>).

Certain Spelling portions of this product is based on Proximity Linguistic Technology. ©Copyright 1990 Merriam-Webster Inc. ©Copyright 1990 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 2003 Franklin Electronic Publishers Inc. ©Copyright 2003 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. Legal Supplement ©Copyright 1990/1994 Merriam-Webster Inc./Franklin Electronic Publishers Inc. ©Copyright 1994 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1990/1994 Merriam-Webster Inc./Franklin Electronic Publishers Inc. ©Copyright 1997 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA ©Copyright 1990 Merriam-Webster Inc. ©Copyright 1993 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 2004 Franklin Electronic Publishers Inc. ©Copyright 2004 All rights reserved.

Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1991 Dr. Lluís de Yzaguirre I Maura ©Copyright 1991 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1990 Munksgaard International Publishers Ltd. ©Copyright 1990 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1990 Van Dale Lexicografie bv ©Copyright 1990 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1995 Van Dale Lexicografie bv ©Copyright 1996 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1990 IDE a.s. ©Copyright 1990 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1992 Hachette/Franklin Electronic Publishers Inc. ©Copyright 2004 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1991 Text & Satz Datentechnik ©Copyright 1991 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 2004 Bertelsmann Lexikon Verlag ©Copyright 2004 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 2004 MorphoLogic Inc. ©Copyright 2004 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1990 William Collins Sons & Co. Ltd. ©Copyright 1990 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1993-95 Russicon Company Ltd. ©Copyright 1995 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 2004 IDE a.s. ©Copyright 2004 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. The Hyphenation portion of this product is based on Proximity Linguistic Technology. ©Copyright 2003 Franklin Electronic Publishers Inc. ©Copyright 2003 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1984 William Collins Sons & Co. Ltd. ©Copyright 1988 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1990 Munksgaard International Publishers Ltd. ©Copyright 1990 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1997 Van Dale Lexicografie bv ©Copyright 1997 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1984 Editions Fernand Nathan ©Copyright 1989 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1983 S Fischer Verlag ©Copyright 1997 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1989 Zanichelli ©Copyright 1989 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1989 IDE a.s. ©Copyright 1989 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1990 Espasa-Calpe ©Copyright 1990 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA. ©Copyright 1989 C.A. Stromberg AB. ©Copyright 1989 All rights reserved. Proximity Technology A Division of Franklin Electronic Publishers, Inc. Burlington, New Jersey USA.

Portions of Adobe Acrobat include technology used under license from Autonomy, and are copyrighted.

Adobe Systems Incorporated, 345 Park Avenue, San Jose, California 95110, USA.

Notice to U.S. government end users. The software and documentation are "Commercial Items," as that term is defined at 48 C.F.R. §2.101, consisting of "Commercial Computer Software" and "Commercial Computer Software Documentation," as such terms are used in 48 C.F.R. §12.212 or 48 C.F.R. §227.7202, as applicable. Consistent with 48 C.F.R. §12.212 or 48 C.F.R. §§227.7202-1 through 227.7202-4, as applicable, the Commercial Computer Software and Commercial Computer Software Documentation are being licensed to U.S. Government end users (a) only as Commercial items and (b) with only those rights as are granted to all other end users pursuant to the terms and conditions herein. Unpublished-rights reserved under the copyright laws of the United States. For U.S. Government End Users, Adobe agrees to comply with all applicable equal opportunity laws including, if appropriate, the provisions of Executive Order 11246, as amended, Section 402 of the Vietnam Era Veterans Readjustment Assistance Act of 1974 (38 USC 4212), and Section 503 of the Rehabilitation Act of 1973, as amended, and the regulations at 41 CFR Parts 60-1 through 60-60, 60-250, and 60-741. The affirmative action clause and regulations contained in the preceding sentence shall be incorporated by reference.

Contents

Before You Begin	5
Chapter 1 Structure Application Definition Reference	9
Contents of an application definition file	9
Define an application	9
Providing default information	11
Specifying the character encoding for SGML files	11
Specifying conditional text output	13
Specifying a DOCTYPE element	13
Specifying a DTD	14
Specifying entities	14
Specifying entities through an entity catalog	15
Specifying the location of individual entities	16
Specifying names for external entity files	17
Specifying public identifiers	18
Specifying a search path for external entity files	19
Specifying external cross reference behavior	20
Change file extension to .XML	20
Try alternative extensions	21
Specifying filename extensions	21
Enabling namespaces	22
Specifying a read/write rules document	22
Specifying a search path for included files in rules documents	22
How FrameMaker searches for rules files	23
Specifying a Schema for XML	23
Specifying an SGML declaration	24
Managing CSS import/export and XSL transformation	24
How the Stylesheets element affects CSS generation	24
How the Stylesheets element affects CSS import	25
How the Stylesheets element affects XSL transformation	25
Specifying a FrameMaker template	26
Specifying a structure API client	27
Specifying the character encoding for XML files	27
Display encoding	28
Encoding of CSS files	29
Exporting XML	29
Limiting the length of a log file	30
Mapping graphic notations to file types	30
Chapter 2 Read/Write Rules Summary	31
All Elements	31
Attributes	32
Books	33
Cross-references	33
Entities	34
Equations	34
Footnotes	35
Graphics	35
Markers	36
Processing instructions	37
Markup documents	37
Tables	38

Text	39	Variables	39
Text insets	39		
Chapter 3 Read/Write Rules Reference	41		
anchored frame	41	include sgml declaration	96
attribute	44	insert table part element	97
character map.	47	is fm attribute.	100
convert referenced graphics	49	is fm char	103
do not include dtd	50	is fm cross-reference element	105
do not include sgml declaration.	51	is fm element	106
do not output book processing instructions.	51	is fm equation element	107
drop	51	is fm footnote element.	108
drop content	53	is fm graphic element	109
element.	54	is fm marker element	111
end vertical straddle	57	is fm property.	112
entity.	59	is fm property value.	119
entity name is.	61	is fm reference element	121
equation	63	is fm rubi element	123
export dpi is	64	is fm rubi group element	124
export to file	67	is fm system variable element	125
external data entity reference	69	is fm table element	126
external dtd	70	is fm table part element	128
facet	72	is fm text inset	129
fm attribute	74	is fm value	131
fm element.	75	is fm variable	133
fm marker	76	is processing instruction	134
fm property	78	line break	134
fm variable.	87	marker text is	136
fm version	89	notation is	137
generate book	89	output book processing instructions	139
implied value is	92	preserve fm element definition	140
include dtd.	94	preserve line breaks	141

processing instruction143	table ruling style is153
proportional width resolution is.144	unwrap154
put element145	use processing instructions156
reader145	use proportional widths156
reformat as plain text146	value157
reformat using target document catalogs147	value is159
retain source document formatting148	write structured document159
specify size in149	write structured document instance only159
start new row151	writer160
start vertical straddle152		

Chapter 4 Conversion Tables for Adding Structure to Documents163

How a conversion table works163	Identifying a sequence to wrap171
Setting up a conversion table164	Providing an attribute for an element.173
Generating an initial conversion table.165	Using a qualifier with an element173
Setting up a conversion table from scratch166	Handling special cases.175
Updating a conversion table166	Promoting an anchored object175
Adding or modifying rules in a conversion table .167		Flagging format overrides176
About tags in a conversion table167	Wrapping untagged formatted text176
Specifying the root element for a structured document168	Nesting object elements177
Identifying a document object to wrap169	Building table structure from paragraph format tags	178
Identifying an element to wrap170	Testing and correcting a conversion table178

Chapter 5 CSS to EDD Mapping181

CSS Font Properties181	CSS Pagination Properties189
CSS text properties184	CSS generated content, automatic numbering, and lists190
CSS color and backgrounds properties185	CSS Tables192
CSS Formatting Model186	CSS Selectors193

Chapter 6 XML Schema to DTD Mapping195

Schema location195	Attributes of simple type elements197
Namespace and Schema location attributes. .196		Complex type mapping198
Simple type mapping196	Group198

Sequence198	Supported Schema features204
Choice199	Defaults.204
All.200	Any204
Named complex types200	Extension and restriction of complex types205
Named attribute groups201	Include, import, and redefine205
Abstract elements202	Unsupported Schema features207
Mixed content models203		
Chapter 7 The CALS/OASIS Table Model209		
FrameMaker properties that DO NOT have corresponding CALS attributes209	Attribute structure213
Element and attribute definition list declarations .210		Inheriting attribute values213
Element structure212	Orient attribute213
		Straddling attributes213
Chapter 8 Read/Write Rules for the CALS/OASIS Table Model215		
Chapter 9 SGML Declaration219		
Text of the default SGML declaration219	Unsupported optional SGML features.222
SGML concrete syntax variants221		
Chapter 10 ISO Public Entities223		
What you need to use ISO public entities.224	Entity read/write rules files225
Entity declaration files225	What happens with the declarations and rules.228
Chapter 11 Character Set Mapping231		
Glossary239		
Index247		

Before You Begin

This developer reference and its associated developer guide are for anybody who develops structured FrameMaker® templates and XML or SGML applications. They are not written for end users who author structured documents that use such templates and applications.

XML and SGML

FrameMaker 9 can read and write XML (Extensible Markup Language) and SGML (Standard Generalized Markup Language) documents. XML and SGML are both document markup languages, and FrameMaker handles these markup languages in similar ways. However, there are differences between the two, and this manual covers these differences whenever necessary.

When discussing the similarities between them, this manual refers to XML and SGML data as *markup data* or *markup documents*. Otherwise, the manual refers to XML and SGML specifically to draw attention to the differences between these markup languages. The majority of new structured documentation projects are XML based, therefore XML now takes precedence over SGML where necessary.

Developing structured FrameMaker templates

End users of FrameMaker can read, edit, format, and write structured documents—the structure is represented by a hierarchical tree of elements. Each structured document is based on a template that contains a catalog of element definitions. Each element definition can describe the valid contexts for an element instance, and the formatting of element instances in various contexts.

To support these end users, you create the catalog and accompanying structured template.

Developing XML and SGML applications

When FrameMaker reads markup data, it displays that data as a formatted, structured document. When the software saves a structured FrameMaker document, the software can write the document as XML or SGML.

For the end user, this process of translation between FrameMaker documents and markup data is transparent and automatic. However, for most XML or SGML document types the translation requires an XML or SGML application to manage the translation. You develop this application to correspond with specific document types. When your end user opens a markup document with a matching document type, FrameMaker invokes the appropriate structure application. If there is no

match for a document type, the user can choose the application to use, or open the markup document with no structure application.

A structure application primarily consists of:

- A structured template
- DTD or schema
- Read/Write rules (described in this manual)
- XSLT style sheets for pre and post process transformations (if necessary)
- An XML and SGML API client (if necessary) developed with the Frame® Developer's Kit (FDK).

Prerequisites

The following topics, which are outside the scope of this manual, are important for you to understand before you try to create a structured template or structure application:

- Structured document authoring in FrameMaker
- XML or SGML concepts and syntax, including how to work with a *document type definition*
- FrameMaker end-user concepts and command syntax
- FrameMaker template design.

In creating some XML or SGML applications, you may also need to understand the following:

- XSLT 1.0
- C programming
- FDK API usage.

If your application requires only the special rules described in this manual to modify the default behavior of FrameMaker, you do not need programming skills. However, if you need to create an XML and SGML API client to modify this behavior further, you need to program the client in C, using the FDK. This manual does not discuss the creation of XML and SGML API clients. For this information, see the *Structure Import/Export API Programmer's Guide*.

Using FrameMaker documentation

FrameMaker comes with a complete set of end-user and developer documentation with which you should be familiar. You can access the FrameMaker guides from the FrameMaker help and support page, <http://www.adobe.com/support/framemaker/>.

If you use the Frame Developer's Kit in creating your structure application, you'll also need to be familiar with the FDK documentation set.

Using this manual

This manual provides detailed reference information for application rules and properties. It can be used in conjunction with the Structure Application Developer Guide. It does not currently include EDD reference information. All EDD descriptive and reference information will be found in the Developer Guide.

Typographical conventions

Monospaced font	Literal values and code, such as XML, SGML, read/write rules, filenames, and pathnames.
<i>Italics</i>	Variables or placeholders in code. For example, in <code>name = "myName"</code> , the text <i>myName</i> represents a value you are expected to supply. Also indicates the first occurrence of a new term.
Blue text	A hyperlink you can click to go to a related section in this book or to a URL in your web browser.
Sans-serif bold	The names of FrameMaker <i>User Interface</i> objects (menus, menu items, and buttons). The > symbol is used as shorthand notation for navigating to menu items and sub menus. For example, Element > Validate... refers to the Validate... item in the Element menu.

Using other FrameMaker documentation

The *Using FrameMaker* makes up the primary end-user documentation for this product. It explains how to use the FrameMaker authoring environment for both structured and unstructured documents. It also explains how to create templates for your documents.

In creating a structured template, you can refer to this manual for information on how your end user interacts with the product and how to create a formatted template.

New features and changes in release 9 (including those for structure applications and structured documents) are listed and briefly described in the *FrameMaker Getting Started Guide*.

You will also find a range of other online documents from the FrameMaker help and support page, <http://www.adobe.com/support/framemaker/>.

Using FDK manuals

If you create an XML and SGML API client for your XML or SGML application, you'll need to be familiar with the FDK. FDK documentation is written for developers with C programming experience.

- *FDK Programmer's Guide* is your manual for understanding FDK basics. This manual describes how to use the FDK to enhance the functionality of FrameMaker and describes how to use the FDK to work with structured documents. To make advanced modifications to the software's default translation behavior, refer to the *Structure Import/Export API Programmer's Guide*.)
- *FDK Programmer's Reference* is a reference for the functions and objects described in the *FDK Programmer's Guide*.
- *Structure Import/Export API Programmer's Guide* explains how to use the FDK to make advanced modifications to the software's default behavior for translation between markup documents and FrameMaker documents. This manual contains both descriptive and reference information.

For information on other FDK manuals, see "Using Frame Developer Tools" in the *FDK Programmer's Guide*.

1

Structure Application Definition Reference

This chapter provides a comprehensive reference for all application properties that can be defined in a structure application definition file.

Contents of an application definition file

The highest-level element in an `structapps.fm` file is `StructuredSetup`. That element's first child must be `Version`, to indicate the FrameMaker version. The `Version` element is followed by zero or more `SGMLApplication` or `XMLApplication` elements, each of which defines the pieces of a structure application. Finally, there can be an optional `Defaults` element, which specifies information used unless overridden for a particular application.

The following table lists the main elements allowed in `structapps.fm` as children of the `StructuredSetup` element. The table identifies the sections that discuss each of those elements and the elements they may contain.

Element	Discussed in
<code>ApplicationName</code>	"Define an application," next
<code>SGMLApplication</code>	"Define an application" on page 9
<code>XMLApplication</code>	"Define an application" on page 9
<code>Defaults</code>	"Providing default information" on page 11

Define an application

FrameMaker collects all information pertaining to the set-up of a structured application into an `SGMLApplication` or `XMLApplication` element. These elements have one required child element and several optional child elements.

The first child of a parent `SGMLApplication` or `XMLApplication` element must be `ApplicationName` and gives the name of the application. It looks like:

Application name: *name*

where *name* is a string used to identify your application in the **Set Structure Application** and **Use Structure Application** dialog boxes. You cannot use the same name for multiple structure applications.

If present, the optional child elements can occur in any order and can include the following elements, discussed in the named sections:

Element	Discussed in
DOCTYPE	"Specifying a DOCTYPE element" on page 13
DTD	"Specifying a DTD" on page 14
CharacterEncoding	"Specifying the character encoding for SGML files" on page 11
ConditionalText	"Specifying conditional text output" on page 13
Entities	"Specifying entities" on page 14
ExternalXRef	"Specifying external cross reference behavior" on page 20
FileExtensionOverride	"Specifying filename extensions" on page 21
Namespace	"Enabling namespaces" on page 22
ReadWriteRules	"Specifying a read/write rules document" on page 22
RulesSearchPaths	"Specifying a search path for included files in rules documents" on page 22
Schema	"Specifying a Schema for XML" on page 23
SGMLDeclaration	"Specifying an SGML declaration" on page 24
Stylesheets	"Managing CSS import/export and XSL transformation" on page 24
Template	"Specifying a FrameMaker template" on page 26
UseAPIClient, UseDefaultAPIClient,	"Specifying a structure API client" on page 27
XMLDisplayEncoding	"Specifying the character encoding for XML files" on page 27
XMLExportEncoding	"Exporting XML" on page 29
XMLCharacterEncoding	"XML character encoding from an SGML application" on page HIDDEN
XMLWriteRules	"Write rules for saving XML from an SGML application" on page HIDDEN

Some elements provide pathnames (for entities and read/write rules files; hence `RulesSearchPaths` and `EntitySearchPaths` elements). If the pathname is absolute, the software looks there. If it can't find it via the specified path, the log reports an error and the operation is aborted. If a relative pathname is given, the software looks for the file in several places:

- The directory containing the file being processed. For example, if you're opening a DTD, the software first searches the directory in which it found the DTD.
- `$STRUCTDIR` (for information on what directory this is, see [Developer Guide, page 131: Location of structure files](#)).
- The directory from which you started FrameMaker.

If an application definition includes any of these elements, the value in the application definition overrides any value for that element in the `Defaults` element. The sections following the next section describe these elements in detail.

Providing default information

Some of the information you provide for individual applications may be common to all your applications. For such information you can specify defaults that are used whenever an application does not provide its own version of the information. You use the `Defaults` element to provide such information.

If present, the optional child elements of `Defaults` can occur in any order (with the exception of the `Graphics` element, which must be the last child) and can include the following elements, which are discussed in the named sections:

Element	Discussed in
<code>CharacterEncoding</code>	“Specifying the character encoding for XML files” on page 27
<code>DTD</code>	“Specifying a DTD” on page 14
<code>Entities</code>	“Specifying entities” on page 14
<code>FrameDefaultAPIClient</code> , <code>UseAPIClient</code>	“Specifying a structure API client” on page 27
<code>MaxErrorMessages</code>	“Limiting the length of a log file” on page 30
<code>Namespace</code>	“Enabling namespaces” on page 22
<code>ReadWriteRules</code>	“Specifying a read/write rules document” on page 22
<code>RulesSearchPaths</code>	“Specifying a search path for included files in rules documents” on page 22
<code>SGMLDeclaration</code>	“Specifying an SGML declaration” on page 24
<code>Stylesheets</code>	“Managing CSS import/export and XSL transformation” on page 24
<code>Template</code>	“Specifying a FrameMaker template” on page 26
<code>XMLCharacterEncoding</code>	“XML character encoding from an SGML application” on page HIDDEN
<code>XMLWriteRules</code>	“Write rules for saving XML from an SGML application” on page HIDDEN
<code>Graphics</code>	“Mapping graphic notations to file types” on page 30

Specifying the character encoding for SGML files

The `CharacterEncoding` element tells the software which encoding to use for the SGML text. Typically, this is only important on non-Western systems, or in SGML applications that encounter SGML files using double-byte text. It can contain one of the following child elements:

ISOLatin1, ASCII, ANSI, MacASCII, ShiftJIS, KSC8EUC, GB8EUC, CNSEUC, Big5, JIS8EUC. The CharacterEncoding element looks like this:

SGML character encoding: Iso Latin1

On a non-Western system, the text for an SGML file can contain double-byte text. This text can be in any one of a number of different text encodings.

FrameMaker can interpret SGML files that contain double-byte text in #PCDATA, RCDATA, and CDATA. The software expects all other text to be within the 7-bit ASCII range (which is supported by all Asian fonts). This means that document content can be in double-byte encodings, but the markup must be in the ASCII range. Typically, for example, the only text in a DTD that will contain double-byte characters would be text used to specify attribute values.

Important: For SGML documents, you should not use accented characters in element tag names nor attribute names. If you use such characters, FrameMaker may not be able to correctly import or export the document.

To import and export SGML that contains double-byte text, you should specify the character encoding to use, either as a default for all applications, or for a specific SGML application. For a given SGML application there can only be one encoding. If you don't specify an encoding for your application, FrameMaker determines the encoding to use by considering the current default user interface language and the current operating system; for the current language, it uses the operating system's default encoding. The default encodings for Windows® are:

Languages	Windows
Roman languages	ANSI
Japanese	Shift-JIS
Simplified Chinese	GB8 EUC
Traditional Chinese	Big5
Korean	KSC8 EUC

You can have an Asian language for the user interface, but the content of the document files in Roman fonts. In this case, any exported Roman text that falls outside of the ASCII range will be garbled. For this reason, we recommend that you specify an encoding for any application that might be used on a non-Western system.

The template for your application must use fonts that support the language implied by the encoding you specify. Otherwise, the text will appear garbled when imported into the template. You can fix this problem after the fact by specifying different fonts to use in the resulting files.

Specifying conditional text output

Add a `ConditionalText` child to the `XMLApplication` element to control conditional text output. Place a single child, `OutputTextPI` in this element. Then add one of the four children listed in the following table to the `OutputTextPI` element:

Child of <code>OutputTextPI</code>	FrameMaker outputs hidden conditional text	Processing instructions delimit conditional text
<code>OutputAllTextWithPIs</code>	yes	yes
<code>OutputAllTextWithoutPIs</code>	yes	no
<code>OutputVisibleTextWithPIs</code>	no	yes
<code>OutputVisibleTextWithoutPIs</code>	no	no

The `ConditionalText` element can only be a child of an `XMLApplication` element.

Specifying a DOCTYPE element

The `DOCTYPE` element specifies the generic identifier of the `DOCTYPE` declaration and root element in markup documents used with this application. If you open a markup document with the matching document element specified in the `DOCTYPE` declaration, FrameMaker uses this application when translating the document. The element looks like:

DOCTYPE: *doctype*

where *doctype* identifies a document element.

For example,

DOCTYPE: chapter

matches a markup document with the following declaration:

```
<!DOCTYPE chapter ...>
```

If more than one application defined in the `structapps.fm` file specifies the same document element, and the end user opens a file with that document element, the software gives the user a choice of which of these applications to use. If the user opens a markup document for which no application specifies its document element, the software gives the user the choice of all defined applications.

You can use more than one `DOCTYPE` element for an application, if that application is applicable to multiple document elements. For example, if the `Book` application applies when the document element is either `chapter` or `appendix`, you can use this definition:

Application name: Book

DOCTYPE: chapter

appendix

...

The DOCTYPE element can be a child of an SGMLApplication or XMLApplication element.

Specifying a DTD

The DTD element specifies a file containing the external DTD subset that FrameMaker uses when importing and exporting a markup document. It looks like:

DTD: *dtd*

where *dtd* is the pathname of a file containing a document type declaration subset.

Note that the file you specify with the DTD element must be an external DTD subset. It cannot be a complete DTD. That is, the file cannot have the form:

```
<!DOCTYPE book [
    <!element book . . .>
    . . .
]>
```

Instead, it should simply have the form:

```
<!element book . . .>
. . .
```

For more information on external DTD subsets, see [Developer Guide, page 89: XML and SGML DTDs](#).

You can have only one DTD element for each SGMLApplication or XMLApplication. It can also be a child of the Defaults element.

Specifying entities

To specify the location of various entities, you use the Entities element. It looks like this:

Entity locations

The possible child elements of a parent Entities element are:

Element	Discussed in
EntityCatalogFile	“Specifying entities through an entity catalog” on page 15
Entity	“Specifying the location of individual entities” on page 16
FileNamePattern	“Specifying names for external entity files” on page 17
Public	“Specifying public identifiers” on page 18
EntitySearchPaths	“Specifying a search path for external entity files” on page 19

If you use the EntityCatalogFile element, you cannot use any of the elements Entity, FileNamePattern, or Public.

You can have only one `Entities` element for each application, although that `Entities` element can have more than one of some of its child elements. The `Entities` element can also be a child of the `Defaults` element.

Specifying entities through an entity catalog

The `EntityCatalogFile` element specifies a file containing mappings of an entity's public identifier or entity name to a filename. It looks like:

Entity locations

Entity catalog file: *fname*

where *fname* is the filename of the entity catalog. Entity catalogs and their specified format are described below.

You can specify multiple `EntityCatalogFile` elements in a single `Entities` element. If you use this element, you cannot use any of the `Entity`, `FilenamePattern`, or `Public` elements.

You can use the `EntityCatalogFile` element both in the `Entities` element of the `Defaults` element and in an `SGMLApplication` or `XMLApplication` element to specify information for a particular application. When searching for an external entity, `FrameMaker` searches the application's entity catalogs before searching the default entity catalogs.

If you have an `EntityCatalogFile` element in an application definition, the software ignores `Entity`, `FilenamePattern`, and `Public` elements in the `Defaults` element.

Why use entity catalogs

Technical Resolution 9401:1994 published by SGML Open discusses entity management issues affecting how SGML documents work with each other:

- Interpreting external identifiers in entity declarations so that an SGML document can be processed by different tools on a single computer system
- Moving SGML documents to different computers in a way that preserves the association of external identifiers in entity declarations with the correct files or other storage objects.

The technical resolution uses *entity catalogs* and an interchange packaging scheme to address these issues. `FrameMaker` supports such entity catalogs with the `EntityCatalogFile` element.

Entity catalog format

Each entry in the entity catalog file associates a filename with information about an external entity that appears in a markup document. For example, the following are catalog entries that associate a public identifier with a filename:

```
PUBLIC "ISO 8879-1986//ENTITIES Added Latin 1//EN" "isolat1.ent"  
PUBLIC "-//USA/AAP//DTD BK-1//EN" "aapbook.dtd"
```

In addition to entries mapping public identifiers to filenames, an entry can associate an entity name with a filename:

```
ENTITY "chips" "graphics\chips.tif"
```

A single catalog can contain both types of entry.

If the specified filename in a catalog entry is a relative pathname, the path is relative to the location of the catalog entry file.

For a complete description of the syntax of a catalog entry, see *Technical Resolution 9401:1994 Entity Management* published by SGML Open.

How FrameMaker searches entity catalogs

A single application may use multiple catalog files. When trying to locate a particular external entity, FrameMaker searches the files one at a time until it finds the entry it is looking for. In each file, the software first searches for an entity using the external entity's public identifier. If the software finds the identifier, it uses the associated filename to locate the entity. If it does not find the public identifier, the software searches the file looking for the entity name. If it does not find the entity name either, the software continues searching in the next catalog file.

In some circumstances, a system identifier specified in an external entity declaration may not be valid. If so, FrameMaker uses public identifier and entity name mappings.

Specifying the location of individual entities

Instead of using an entity catalog to associate entities with files, you can use the `Entity` element as a child of a parent `Entities` element. This element allows you to directly associate a filename with an individual entity. It looks like:

Entity locations

Entity name: *ename*

Filename: *fname*

where *ename* is the name of an entity and *fname* is a filename.

You can specify multiple child `Entity` elements for a single `Entities` element. You use the `FilenamePattern` and `EntitySearchPaths` elements to help the software find these files.

The `Entity` element can be a child of a parent `Entities` element in the `Defaults` element to set default entity information, and of a parent `SGMLApplication` or `XMLApplication` element to specify information for a particular application. When searching for an external entity, the software searches the application's entity locations before searching the default entity locations.

Specifying names for external entity files

One or more `FilenamePattern` elements can appear as a child of a parent `Entities` element to tell the software how to locate an external entity.

A `FilenamePattern` element does not apply to an entity for which there is an `Entity` element. Otherwise, it applies to all external entities except those with an external identifier that includes a public identifier but no system identifier. The `FilenamePattern` looks like:

Entity locations:

Filename pattern: *pattern*

where *pattern* is a string representing a device-dependent filename. The three variables that can appear within *pattern* are interpreted as follows:

Variable	Interpretation
<code>\$(System)</code>	The system identifier from the entity declaration
<code>\$(Notation)</code>	The notation name from the entity declaration of an external data entity
<code>\$(Entity)</code>	The entity name

Case is not significant in variable names, although it may be significant in the values of the variables. If a variable is undefined in a particular context, that variable evaluates to the empty string.

A parent `Entities` element can contain multiple child `FilenamePattern` elements. The software assumes the last pattern in the `Entities` element is:

Filename pattern: `$(System)`

Thus, if no `FilenamePattern` elements appear or even if no `Entities` element appears, the software assumes system identifiers are complete pathnames and will check search paths to locate the file.

How FrameMaker searches filename patterns

When locating an external entity, FrameMaker tests the value of the *pattern* arguments in successive `FilenamePattern` elements that have the same parent `Entities` element, in the order they occur, until it finds the name of an existing file. As it tests each *pattern*, it substitutes relevant information from the entity's declaration for variables in *pattern*.

You can use the `FilenamePattern` element both in the `Entities` element of the `Defaults` element and in an `SGMLApplication` element to specify information for a particular application. When searching for an external entity, FrameMaker tests all the filename patterns specified for the application before it tests those in default `FilenamePattern` elements.

Example

Suppose the `Entities` element looks like:

Entity locations:

Filename pattern: `$(System).sgm`

Filename pattern: `$(System).$(Notation)`

and the markup document contains:

```
<!ENTITY intro SYSTEM "introduction.xml">
<!ENTITY chips SYSTEM "chipsfile" NDATA cgm>
. . .
&intro;
. . .
<graphic entity=chips>
```

When processing the reference to `intro`, the software searches for a file called `introduction.xml`. It is an error if the file does not exist.

When processing the `entity` attribute of the `graphic` element, FrameMaker searches for a file named `chipsfile.cgm`. If one is not found, it then looks for `chipsfile.CGM`, assuming that the `NAMECASE GENERAL` parameter of the associated SGML declaration is `NAMECASE GENERAL YES`.

Note: The `NAMECASE GENERAL` parameter of the SGML declaration determines the case-sensitivity of notation names. For XML, the implied setting for this parameter is `NO`, which means that names are case-sensitive.

For SGML, the value of this parameter in the reference concrete syntax is `NAMECASE GENERAL YES`. With this declaration, the SGML parser forces notation names to uppercase.

Specifying public identifiers

The `Public` element of an `Entities` element tells the software how to process an external identifier that has a public identifier but no system identifier. It looks like:

Entity locations:

Public ID: `pid`

Filename: `fname`

where `pid` is a public identifier and `fname` is the name of a file to be associated with the entity using the public identifier.

You can give multiple `Public` elements in the same parent `Entities` element. If you want to give multiple filenames to search for a particular public identifier, you can specify the same public identifier in multiple `Public` elements.

You can use the `Public` element both in the `Entities` element of the `Defaults` element and in an `Entities` element of an `SGMLApplication` or `XMLApplication` element to specify information for a particular application. If a `Public` element occurs as a child of an `SGMLApplication` or `XMLApplication` element, that identifier is used in preference to one occurring as a child of the `Defaults` element.

Specifying a search path for external entity files

The `EntitySearchPaths` child of a parent `Entities` element tells the software what directories to search for the files indicated by `Entity`, `FilenamePattern`, and `Public` elements. It looks like:

Entity locations:

Entity search paths

1: `directory1`

...

N: `directoryn`

where each `directoryi` is a device-dependent directory name. The three variables and their abbreviations that can be used to specify a directory are as follows:

Variable	Abbreviation	Interpretation
<code>\$HOME</code>	<code>~</code>	The user's home directory
<code>\$SRCDIR</code>	<code>.</code>	The directory containing the document entity being processed
<code>\$STRUCTDIR</code>		The structure directory in use (for information on what directory this is, see Developer Guide, page 131: Location of structure files)

Each `directoryi` value can be an absolute pathname or relative to `$SRCDIR`.

How FrameMaker searches for entity files

To locate an external entity, FrameMaker searches the specified directories in the order listed. You can use the `EntitySearchPaths` element both in the `Entities` element of the `Defaults` element and in an `XMLApplication` or `SGMLApplication` element. When searching for an external entity, FrameMaker searches the directories named in the `EntitySearchPaths` element for the application before it searches those in a default `EntitySearchPaths` element.

An `Entities` element can contain only one `EntitySearchPaths` element. The software assumes the `EntitySearchPaths` element ends this way:

Entity search paths

...

N: `$SRCDIR`

Thus, if there is no `EntitySearchPaths` element, the software assumes all markup files are in the same directory.

Example

Assume the `Defaults` element is defined as follows:

Defaults

Entity locations:

Filename pattern: `$(System).sgm`

Filename pattern: `$(System).$(Notation)`

Entity search paths

1: `$HOME`

2: `$SRCDIR`

and the markup document contains:

```
<!ENTITY intro SYSTEM "introduction.xml">
<!ENTITY chips SYSTEM "chipsfile" NDATA cgm>
. . .
&intro;
. . .
<graphic entity=chips>
```

When processing the reference to `intro`, the software looks for the files:

```
$HOME/introduction.xml
$SRCDIR/introduction.xml
```

until it finds one of those files. When processing the `graphic` element, the software searches in order for:

```
$HOME/chipsfile.cgm
$SRCDIR/chipsfile.cgm
```

Specifying external cross reference behavior

To ensure correct resolution of external cross references in XML, use the `ExternalXRef` element. `ExternalXRef` can only be a child of `XMLApplication`.

Change file extension to .XML

Insert an `ExternalXRef` child in the `XMLApplication` element for the application you are developing. In this `ExternalXRef` element, insert a `ChangeReferenceToXML` child. Finally, insert an `Enable` element into the `ChangeReferenceToXML` element. It will look like this:

External X-Ref:

Change Reference To .XML: Enable

When a document with an external cross-reference is saved to XML, FrameMaker then changes the extension in the `xref's srcfile` attribute to `.xml` and exports the cross-reference as:

```
<xref srcfile="filepath/filename.xml#elemID">
```

Where:

- `filepath` is the absolute path to the saved source XML file
- `filename` is the name of the saved source XML file
- `elemID` is the ID of the referenced element.

You can save the source file to XML before or after saving the original file to XML. In either case, the file name specified for the XML document must be identical to the filename of the original FrameMaker document except for the extension.

If you insert a `Disable` element instead of an `Enable` element into `ChangeReferenceToXML`, FrameMaker retains the default behavior and does not change the extension in the `srcfile` attribute.

Try alternative extensions

`TryAlternativeExtensions` specifies an option for importing external cross-references from XML. It looks like this:

External X-Ref:

Try Alternative Extensions: Enable

If its content is `Enable`, and FrameMaker cannot open the file specified by the `srcfile` attribute, it changes the extension and tries to open the resulting file instead. In particular, if the original extension is `.xml`, FrameMaker also tries `.fm`; if the original extension is `.fm`, FrameMaker also tries `.xml`. If the content of `TryAlternativeExtensions` is `Disable`, FrameMaker creates an unresolved cross-reference if the specified file cannot be opened. `Disable` is the default.

Specifying filename extensions

The `FileExtensionOverride` element specifies a filename extension to use when saving a FrameMaker document as markup. This is particularly useful when saving XHTML documents. Some web browsers that support XHTML can only read files with a `.htm` or `.html` extension. When you save a document as XML (even using the XHTML doctype) FrameMaker gives the file a `.xml` extension by default. You can use this element to specify a `.htm` extension when saving a document as XHTML. The `FileExtensionOverride` element looks like this:

File Extension Override: *extension*

where *extension* is the string for the filename extension, minus the dot character. You can have only one `FileExtensionOverride` element for each XML or SGML structure application.

Enabling namespaces

The `Namespace` element specifies whether the current XML structure application supports namespaces in XML. This element can contain either an `Enable` or `Disable` child element. The `Namespace` element looks like this with namespaces enabled:

Namespace: *Enable*

You can have only one `Namespace` element for each XML structure application. It can also be a child of the `Defaults` element. It is not applicable for an SGML application.

Note: XML Schema: You must enable namespaces to allow FrameMaker to validate XML against a Schema definition upon import and export. Schema allows an XML document to reference multiple Schema locations in different namespaces. When this is the case, only the first namespace is used. See [Developer Guide, page 195: Schema location](#) for additional information.

Specifying a read/write rules document

The `ReadWriteRules` element specifies the read/write rules document associated with the application. It looks like:

Read/write rules: *rules*

where *rules* is the pathname of a FrameMaker read/write rules document.

You can have only one `ReadWriteRules` element for each application. It can also be a child of the `Defaults` element.

Specifying a search path for included files in rules documents

The `RulesSearchPaths` element is analogous to the `EntitySearchPaths` element, but it pertains to additional files you include in a read/write rules document rather than to external entities referenced within a markup document. Its `Path` child elements indicate individual directories. It looks like:

Search paths for included read/write rules files:

1: *directory₁*

...

N: *directory_n*

where each *directory_i* is a device-dependent directory name. The two variables and their abbreviations that can be used to specify a directory are as follows:

Variable	Abbreviation	Interpretation
\$HOME	~	The user's home directory
\$STRUCTDIR		The structure directory in use (for information on what directory this is, see Developer Guide, page 131: Location of structure files)

Each *directory_i* value can be an absolute pathname or relative to \$RULESDIR.

How FrameMaker searches for rules files

Only one RulesSearchPaths element can occur as the child of a single parent XMLApplication or SGMLApplication element or parent Defaults element. When searching for a file you include in an read/write rules document, FrameMaker searches the directories named in the RulesSearchPaths element for the application before it searches those in the RulesSearchPaths element of the Defaults element.

The software assumes RulesSearchPaths ends in this way:

Search paths for included read/write rules files:

...

N: \$RULESDIR

Thus, if there is no RulesSearchPaths element, the software assumes all files you include in the read/write rules document are in the same directory as your rules document.

Specifying a Schema for XML

The Schema element, a direct child of XMLApplication, specifies the path and filename for an XML Schema file that contains element declarations for XML. It look like this:

Schema: *schema_path*

where *schema_path* is the pathname of a file containing a Schema declaration file.

In order for a structure application to be selectable in the Use Structured Application list while importing a document that is associated with a Schema, the Schema's root element must be included in the application's DOCTYPE in the XmlApplication element.

Specifying an SGML declaration

The `SGMLDeclaration` element specifies the location of a file containing a valid SGML declaration. It is used only for SGML applications and cannot be a child of an `XMLApplication` element. The `SGMLDeclaration` element looks like:

SGML declaration: *declaration*

where *declaration* is the pathname of the SGML declaration file.

You can have only one `SGMLDeclaration` element for each SGML application. It can also be a child of the `Defaults` element.

Managing CSS import/export and XSL transformation

The `Stylesheets` element of an XML structure application tells the software how to treat the use of CSS stylesheets for a given XML document, and how and whether to perform XSL transformation upon import or export of XML documents.

An XML application can have only one `Stylesheets` element. It can also be a child of the `Defaults` element.

How the Stylesheets element affects CSS generation

You can specify whether to use an existing stylesheet, or whether FrameMaker should generate a new one and use that for the exported XML. You can specify any number of stylesheets, and the exported XML will include references to each one. The `Stylesheets` element also contains instructions concerning the use of attributes and stylesheet processing instructions. The `Stylesheets` element for CSS looks like:

CSS2 Preferences:

Generate CSS2: *enable/disable*

Add Fm CSS Attribute To XML: *enable/disable*

Retain Stylesheet Information: *enable/disable*

XML Stylesheet:

Type: *stylesheet_type*

URI: *path*

When you save a document to XML, FrameMaker can either use an existing stylesheet, or generate a new one from the current EDD. How FrameMaker generates a stylesheet is determined by the values of the children of the `Stylesheets` element. For more information about how FrameMaker converts EDD information into a stylesheet, see [Developer Guide, page 281: Saving EDD Formatting Information as a CSS Stylesheet](#)

GenerateCSS2 Specifies whether FrameMaker will generate a CSS when you save the document as XML. It can be set to *enable* or *disable*. When this is set to *enable*, FrameMaker generates a CSS. If a path is provided in `StylesheetURI`, FrameMaker saves the stylesheet to that location, with

that filename. Otherwise, it saves the stylesheet to the same location as the XML document with a filename *xmlDoc.css*, where *xmlDoc* is the name of the XML document you're saving.

AddFmCSSAttrToXml Specifies whether FrameMaker will write instances of the `fmcssattr` attribute to elements in the XML document. It can be set to `enable` or `disable`. An EDD can include context selectors as criteria to assign format rules. CSS has no equivalent to this. When this is set to `enable`, FrameMaker uses the `fmcssattr` attribute in certain elements so the CSS can achieve the same formatting as the EDD.

RetainStylesheetPIs Specifies whether FrameMaker will retain the stylesheet declaration for import and export of XML. It can be set to `enable` or `disable`. When this is set to `enable`, FrameMaker does the following:

- On import, it stores the XML document's stylesheet PI as a marker in the FrameMaker document.
- On export, it writes the content of stylesheet PI marker in the resulting XML document.

StylesheetType Specifies the type of stylesheet. It contains a string for the stylesheet type. Currently, you can specify `CSS` (upper or lower case) or `XLS` (upper or lower case). If you specify `XLS`, FrameMaker will not generate a stylesheet.

StylesheetURI Specifies the URI for the stylesheet. It contains a string; for example, `/ $STRUCTDIR/xml/xhtml/app/xhtml.css`.

How the Stylesheets element affects CSS import

You can specify whether a CSS stylesheet that is referenced in an XML file is used to update the formatting of the FrameMaker document. The `ProcessStylesheetPI` is an optional child of the `CssPreferences` element and looks like this:

CSS2 Preferences:

ProcessStylesheetPI: *enable/disable*

`ProcessStylesheetPI` can have one of the following values: `Enable` or `Disable`. If the value of the `ProcessStylesheetPI` element is `Enable`, then the CSS file referenced in the XML file is used while opening the XML file. The default value of the `ProcessStylesheetPI` element is `Disable`.

For more information about how the CSS file mentioned in the XML file is used when an XML file is opened, see [Chapter 5, "CSS to EDD Mapping."](#)

How the Stylesheets element affects XSL transformation

If an XML structure application specifies an XSL stylesheet, FrameMaker can apply transformations defined in that stylesheet when importing an XML document, or when exporting a FrameMaker document to XML. The `XSLTPreferences` element in the `Stylesheets` element allows you to specify the XSL file to use for transformation upon import (`PreProcessing`) and/or export

(`PostProcessing`). `StylesheetParameters` elements allow you to set parameters of an XSL stylesheet at run time, before the transformation takes place.

XSLT Preferences:

Process Stylesheet PI: enable/disable

Preprocessing:

Stylesheet: *path*

Stylesheet Parameters

Name: *parameter name*

Expression: *exp*

Postprocessing:

Stylesheet: *path*

Stylesheet Parameters

Name: *parameter name*

Expression: *exp*

ProcessStylesheetPI Specifies whether FrameMaker will use the XSL file mentioned in the `xml-stylesheet` PI of an XML file to transform that file. It can be set to `enable` or `disable`. By default it is set to `disable`, and FrameMaker does not use the PI. Set to `enable` to use the PI.

PreProcessing Contains a `Stylesheet` element that specifies the XSL file to be used for transformation upon import of an XML document. Transformation occurs before read rules are applied. The `XSLTPreferences` element can contain 0 or 1 `PreProcessing` elements.

PreProcessing Contains a `Stylesheet` element that specifies the XSL file to be used for transformation upon export of an XML document. Transformation occurs after write rules are applied. The `XSLTPreferences` element can contain 0 or 1 `PostProcessing` elements.

Stylesheet Specifies the URI for the XSL file. It contains a string; for example, `/ $STRUCTDIR/xml/xhtml/app/mystyles.xsl`.

StylesheetParameters Contains `ParameterName` and `ParameterExpression` pairs. Each pair specifies the name of a parameter used the XSL stylesheet, and an expression that constrains the value of that parameter for the subsequent transformation.

For more information on XSL transformation of XML, see [Developer Guide, Chapter 29, Additional XSL Transformation for XML](#).

Specifying a FrameMaker template

The `Template` element specifies the location of the FrameMaker template. It looks like:

Template: *template*

where *template* is the pathname of a FrameMaker template.

The software uses this template to create new FrameMaker documents from markup documents, which may be single documents resulting from the `Open` or `Import` command or documents in a book created through the `Open` command.

If this element is not present, the software creates new portrait documents as needed. When you import a markup document into an existing document, the software uses the import template only to access reference elements that are stored on the template's reference page. (For information about reference elements, see [Developer Reference, page 330: Translating SDATA entities as FrameMaker reference elements.](#))

You can have only one `Template` element for each application. It can also be a child of the `Defaults` element.

Specifying a structure API client

In an application definition, the `UseDefaultAPIClient` element tells the software that your application does not use a special client for markup translation. In the defaults section, the `FrameDefaultAPIClient` element serves the same purpose. The default client is named `FmTranslator`.

If you do need a structure API client, use the `UseAPIClient` element in either context. For information on creating structure API clients for a structure application, see the online manual *Structure Import/Export API Programmer's Guide*.

Specifying the character encoding for XML files

The XML specification supports UNICODE characters for document content and markup tokens. In XML the given encoding is specified in the document prolog. The following example shows a specification for ShiftJIS character encoding:

```
<?xml version="1.0" encoding="Shift_JIS" ?>
```

The XML specification states that an XML document must either specify an encoding in the prolog, or it must be UTF-8 or UTF-16. FrameMaker follows this specification by assuming UTF-8 by default if there is no encoding specified in the XML file.

If you read an XML file with character encoding that does not match either the declared encoding or the default encoding (if no encoding is declared), it is likely that the import process will encounter a character that does not match the encoding FrameMaker uses. In that case, you will get a parsing error that says the document is not well-formed due to a bad token.

FrameMaker uses the encoding statement in the document prolog to determine which encoding to use. The statement must specify one of the encodings supported by your specific FrameMaker installation. FrameMaker ships with support for the following encodings:

Big5	KSC_5601
EUC-JP	Shift_JIS
EUC-KR	US-ASCII
EUC-TW	UTF-16
GB2312	UTF-8

ISO-8859-1 windows-1252

You can add other encodings to your FrameMaker installation—see [Developer Guide, page 103: Unicode and character encodings](#).

FrameMaker converts the encoding of the XML document to an internal display encoding. In this way FrameMaker fully supports Unicode characters for text that is in #PCDATA, RCDATA, and CDATA. For any #PCDATA character that it cannot interpret, FrameMaker uses a marker of type UNKNOWNCHAR to represent the character. For unknown CDATA characters, FrameMaker uses XML character references.

The following sections describe how to control the display encoding that FrameMaker uses, and how to specify an encoding when you save a document as XML.

Display encoding

On import, FrameMaker converts the XML encoding to a display encoding that is appropriate for a given language. However, FrameMaker cannot automatically determine which conversion to make. Although the XML document prolog specifies an encoding, the document may contain elements or other constructs that override the language implied by that encoding. As a result, you should specify a display encoding for the structure application. The display encodings you can specify are:

Display encoding:	For this language:
FrameRoman	Western European languages
JISX0208.ShiftJIS	Japanese
BIG5	Traditional Chinese
GB2312-80.EUC	Simplified Chinese
KSC5601-1992	Korean

By default, FrameMaker uses the display encoding that matches the locale of your operating system. To specify a different display encoding, use the `XmlDisplayEncoding` element. `XmlDisplayEncoding` can contain one child element to specify one of the supported display encodings.

The display encoding also determines how FrameMaker interprets the characters in markup tokens such as GIs and attribute names. If FrameMaker encounters such a token with an unknown character, FrameMaker drops the token. For more information, see [Developer Guide, page 101: Supported characters in element and attribute names](#).

For example, if your operating system locale is French, German, or English FrameMaker uses FrameRoman by default. This is true, even if the XML prolog specifies an encoding for a different language, such as ShiftJIS. To import XML encoded as ShiftJIS, you would use the `XmlDisplayEncoding` element to specify JISX0208.ShiftJIS, as follows:

XML Display Encoding: JISX0208.ShiftJIS

When you specify such an encoding, FrameMaker uses that encoding as the default for all the `#PCDATA`, `RCDATA`, and `CDATA` in the imported XML. Markup tokens that include characters in the upper range of the display encoding are interpreted correctly. If you have fonts installed for the display encoding, then the text will appear as intended.

For another example, assume you have a version of US English FrameMaker installed on a Traditional Chinese operating system. By default, FrameMaker uses Big5 as the display encoding. It also supports any Big5 characters that are used in GIs and attribute names. If you are importing an XML document that is in English, you would need to specify FrameRoman as the display encoding.

Note that the XML standard includes the `xml:lang` attribute. This attribute can specify a change of language for an element and its content. If that language is one of those listed in the table of display encodings, a change made by this attribute take precedence over the setting made via `XmlDisplayEncoding`.

Finally, the template for your application must use fonts that support the given language. Otherwise, the text will appear garbled when imported into the template. You can fix this problem by specifying different fonts to use in the resulting files.

Encoding of CSS files

FrameMaker supports the following encodings for CSS files: utf-8, utf-16, utf-16LE, and utf-16BE. FrameMaker detects the encoding of a CSS file using the Byte Order Mark (BOM), and not the “@charset” statement.

Exporting XML

Your XML structure application can include an `XmlExportEncoding` element to specify the encoding to use when you save a document as XML. FrameMaker determines which encoding to use according to the following rules:

If:	FrameMaker uses:
1 The structure application specifies a value for <code>XmlExportEncoding</code> , and that encoding is supported	The specified encoding
2 1 is not true, and the original XML source specified an encoding, and that encoding is supported	The encoding that was specified in the original XML source
3 1 and 2 are not true	UTF-8

The `XmlExportEncoding` element contains a string for the name of an encoding. The name you provide must conform with the IANA naming conventions. The standard installation of FrameMaker supports the encodings that are listed at the beginning of this discussion (see [page 27](#)).

For example, to export your document as ISOLatin1, use the `XmlExportEncoding` element as follows:

XML Export Encoding: ISO-8859-1

Limiting the length of a log file

The `MaxErrorMessage` child element of the `Defaults` element allows you to limit the length of structure error reports. It looks like:

Maximum number of error messages: n

where n is the desired limit. If n is less than 10, the software resets it to 10. This must be the last child of the parent `Defaults` element.

By default, FrameMaker does not write more than 150 messages (error messages and warnings) to a single log file.

Messages pertaining to opening and closing book components are not included in this limit. Messages generated through your own structure API client are also not counted, although if you wish, you can count them using your own code.

In documents that generate large numbers of messages, the 151st message is replaced with a note that additional messages have been suppressed.

Note that processing continues, even though further messages are not reported. This message limit is reset for every file processed and for each component of a book.

Mapping graphic notations to file types

The `Graphics` child element of the `Defaults` element allows you to provide mappings from graphic notation to file type by using the file name extension. In the example below the `JPEG` notation is mapped to the `.jpg` extension.

Graphics

Notation: JPEG **Filetypehint:**jpg

The `Graphics` element may contain one or more `Mapping` elements.

2

Read/Write Rules Summary

This chapter lists the available read/write rules by category and briefly describes the purpose of each rule. The categories, which are arranged alphabetically, are as follows:

- “All Elements” on page 31
- “Attributes” on page 32
- “Books” on page 33
- “Cross-references” on page 33
- “Entities” on page 34
- “Equations” on page 34
- “Footnotes” on page 35
- “Graphics” on page 35
- “Markers” on page 36
- “Processing instructions” on page 37
- “Markup documents” on page 37
- “Tables” on page 38
- “Text” on page 39
- “Text insets” on page 39
- “Variables” on page 39.

All Elements

To	Use this rule	Page
Translate a markup element	<code>element</code>	54
Discard or unwrap a FrameMaker element on export	<code>fm element</code>	75
Translate a markup element to a FrameMaker element	<code>is fm element</code>	106
Translate a markup attribute within the context of a single markup element	<code>attribute</code>	44

To	Use this rule	Page
Inform FrameMaker not to update a FrameMaker element's definition when updating an existing EDD	<code>preserve fm element definition</code>	140
Discard a FrameMaker or markup element	<code>drop</code>	51
Discard the content but not the structure of a FrameMaker or markup element	<code>drop content</code>	53
Discard the structure but not the content of a markup or FrameMaker element	<code>unwrap</code>	154

Attributes

To	Use this rule	Page
Translate a markup attribute	<code>attribute</code>	44
Discard a FrameMaker attribute	<code>fm attribute</code>	74
Translate a markup attribute to a FrameMaker attribute	<code>is fm attribute</code>	100
Translate a markup attribute within the context of a single markup element	<code>element</code>	54
Discard a markup or FrameMaker attribute	<code>drop</code>	51
Translate a markup attribute to a particular FrameMaker property	<code>is fm property</code>	112
Translate a value for a markup attribute to a FrameMaker property value	<code>is fm property value</code>	119
Translate a value of a markup notation attribute or name token group to a value for a FrameMaker choice attribute	<code>is fm value</code>	131
Translate a markup attribute value to a FrameMaker property or a choice attribute value	<code>value</code>	157
Specify the value to use for a markup implied attribute when a document instance provides no value	<code>implied value is</code>	92

Books

To	Use this rule	Page
Specify whether to use elements or processing instructions to indicate book components when reading a markup document	<code>generate book</code>	89
Specify elements to use to indicate book components when reading a markup document	<code>put element</code> (described with generate book)	89
Specify the use of processing instructions to indicate book components when reading a markup document	<code>use processing instructions</code> (described with generate book)	89
Specify whether or not to write processing instructions that indicate book components in a markup document	<code>output book processing instructions</code>	139

Cross-references

To	Use this rule	Page
Translate markup elements to FrameMaker cross-reference elements	<code>is fm cross-reference element</code>	105
Translate FrameMaker cross-reference properties when no markup attribute exists	<code>fm property</code>	78
Translate FrameMaker cross-reference properties when no markup attribute exists	<code>value is</code> (described with fm property)	78
Translate a markup attribute to a particular FrameMaker property	<code>is fm property</code>	112
Translate a value for a markup attribute to a FrameMaker property value	<code>is fm property value</code>	119
Translate a value of a markup notation attribute or name token group to a value for a FrameMaker choice attribute	<code>is fm value</code>	131
Translate a FrameMaker cross-reference element to text in markup	<code>fm element unwrap</code>	75, 154

Entities

To	Use this rule	Page
Translate a markup entity reference to an appropriate FrameMaker representation	entity	59
Determine the form of names of entities created for exported graphics	entity name is	61
Drop references to external data entities	external data entity reference	69
Translate an entity reference to a FrameMaker variable	is fm variable	133
Translate an entity reference to a single character	is fm char	103
Translate an entity reference to an element on a reference page	is fm reference element	121
Translate an SDATA entity reference to a text inset	is fm text inset	129
Determine the formatting of a text inset	reformat as plain text	146
	reformat using target document catalogs	147
	retain source document formatting	148
Discard external data entity references	drop	51

Equations

To	Use this rule	Page
Translate a markup element to a FrameMaker equation element	is fm equation element	107
Specify export information for translating FrameMaker equations	equation	63
Specify the filename used for exporting an equation	export to file	67
Determine the form of names of entities created for exported equations	entity name is	61
Specify the data content notation for an exported equation	notation is	137

To	Use this rule	Page
Determine whether FrameMaker uses the <code>dpi</code> attribute or the <code>impsize</code> attribute for equations and also the resolution used	<code>specify size in</code>	149
Translate FrameMaker cross-reference properties when no markup attribute exists	<code>fm property</code>	78
Translate FrameMaker cross-reference properties when no markup attribute exists	<code>value is</code> (described with fm property)	78
Translate FrameMaker equation properties to markup attributes	<code>is fm property</code>	112
Translate a value for a markup attribute to a FrameMaker property value	<code>is fm property value</code>	119
Translate a value of a markup notation attribute or name token group to a value for a FrameMaker choice attribute	<code>is fm value</code>	131
Translate a markup attribute value to a FrameMaker property or a choice attribute value	<code>value</code>	157

Footnotes

To	Use this rule	Page
Translate a markup element to a FrameMaker footnote element	<code>is fm footnote element</code>	108

Graphics

To	Use this rule	Page
Translate a markup element to a FrameMaker graphic element	<code>is fm graphic element</code>	109
Specify export information for translating FrameMaker graphics	<code>anchored frame</code>	41
Specify export information for translating FrameMaker graphics that have a single inset	<code>facet</code>	72
Specify the filename used for exporting a graphic or a facet of a graphic	<code>export to file</code>	67
Force the software to export graphic files that were imported by reference	<code>convert referenced graphics</code>	49

To	Use this rule	Page
Determine the form of names of entities created for exported graphics	entity name is	61
Specify the data content notation for an exported graphic	notation is	137
Determine whether FrameMaker uses the <code>dpi</code> attribute or the <code>impsize</code> attribute for imported graphics objects and also the resolution used	specify size in	149
Translate FrameMaker cross-reference properties when no markup attribute exists	fm property	78
Translate FrameMaker cross-reference properties when no markup attribute exists	value is (described with fm property)	78
Translate FrameMaker graphic properties to markup attributes	is fm property	112
Translate a value for a markup attribute to a FrameMaker property value	is fm property value	119
Translate a value of a markup notation attribute or name token group to a value for a FrameMaker choice attribute	is fm value	131
Translate a markup attribute value to a FrameMaker property or a choice attribute value	value	157

Markers

To	Use this rule	Page
Discard FrameMaker non-element markers or translate them to processing instructions	fm marker	76
Translate a markup element to a FrameMaker marker element	is fm marker element	111
Determine whether marker text for marker elements becomes content or an attribute value in markup	marker text is	136
Drop references to external data entities	external data entity reference	69
Drop unrecognized processing instructions	processing instruction	143
Translate FrameMaker non-element markers to processing instructions	is processing instruction	134
Discard non-element markers	drop	51

To	Use this rule	Page
Translate FrameMaker cross-reference properties when no markup attribute exists	fm property	78
Translate FrameMaker cross-reference properties when no markup attribute exists	value is (described with fm property)	78
Translate FrameMaker marker properties to markup attributes	is fm property	112
Translate a value for a markup attribute to a FrameMaker property value	is fm property value	119
Translate a value of a markup notation attribute or name token group to a value for a FrameMaker choice attribute	is fm value	131
Translate a markup attribute value to a FrameMaker property or a choice attribute value	value	157

Processing instructions

To	Use this rule	Page
Specify the treatment of unrecognized processing instructions	processing instruction	143
Specify the use of processing instructions to indicate book components when reading a markup document	use processing instructions (described with generate book)	89
Specify whether or not to write processing instructions that indicate book components in a markup document	output book processing instructions	139
Translate FrameMaker non-element markers to specific markup, or drop them	fm marker	76
Translate FrameMaker non-element markers to processing instructions	is processing instruction	134
Discard processing instructions	drop	51

Markup documents

To	Use this rule	Page
Specify whether or not to use an external DTD subset to contain the DTD for a markup document created by FrameMaker	include dtd	94

To	Use this rule	Page
Specify whether or not to include an SGML declaration in an SGML document created by FrameMaker	<code>include sgml declaration</code>	96
Specify the system and public identifiers for an external DTD subset	<code>external dtd</code>	70
Specify whether to create an entire markup document or just a markup document instance	<code>write structured document</code> <code>write structured document instance only</code>	159 159

Tables

To	Use this rule	Page
Translate a markup element to a FrameMaker table element	<code>is fm table element</code>	126
Translate a markup element to a FrameMaker element for a particular table part	<code>is fm table part element</code>	128
When creating a FrameMaker table, insert a table part even if that part is empty	<code>insert table part element</code>	97
Specify that a particular element always indicates a new table row	<code>start new row</code>	151
Indicate the start of a vertical straddle	<code>start vertical straddle</code>	152
Indicate the end of a vertical straddle	<code>end vertical straddle</code>	57
Specify the ruling style used for all tables	<code>table ruling style is</code>	153
Specify the resolution used for column widths with proportional widths	<code>proportional width resolution is</code>	144
Specify that the software write the width of table columns using proportional units	<code>use proportional widths</code>	156
Translate FrameMaker table properties to markup attributes	<code>is fm property</code>	112
Translate a value for a markup attribute to a FrameMaker property value	<code>is fm property value</code>	119
Translate a value of a markup notation attribute or name token group to a value for a FrameMaker choice attribute	<code>is fm value</code>	131
Translate an attribute's name token value to a FrameMaker property or choice value	<code>value</code>	157

Text

To	Use this rule	Page
Translate an entity reference to a single character	is fm char	103
Determine the treatment of line breaks in reading and writing markup documents	line break	134
Define mappings between characters in the markup and FrameMaker character sets	character map	47

Text insets

To	Use this rule	Page
Translate an SDATA entity reference to a FrameMaker text inset	entity	59
	is fm text inset	129
Determine the formatting of a text inset	reformat as plain text	146
	reformat using target document catalogs	147
	retain source document formatting	148

Variables

To	Use this rule	Page
Translate a markup element to a FrameMaker system variable element	is fm system variable element	125
Translate an entity reference to a FrameMaker variable	is fm variable	133
Translate a markup entity reference to a FrameMaker variable	entity	59
Determine treatment of FrameMaker non-element variables	fm variable	87
Translate a FrameMaker system variable element to text in markup	fm element unwrap	75, 154
Discard nonelement variables	drop	51

3

Read/Write Rules Reference

This chapter provides a reference to all read/write rules, listed in alphabetical order. The entry for each rule starts with a brief explanation of the purpose of the rule and how to use it. The rule's description may include the following sections:

Synopsis and contexts The rule's syntax and the context in which it can be used. If the rule occurs as a subrule of another rule, the more general rule is shown. If the rule can be used in multiple contexts, the synopsis shows each context. Each entry in this section shows a valid rule that has the current rule either at the highest level or as one of its subrules.

Rule synopses use the following conventions:

- Bold portions and nonitalicized portions of a rule are entered by you as shown.
- Italicized portions of a rule indicate the rule's arguments or possible subrules; you enter your values.
- Brackets [] indicate optional parts of a rule; the entire form within the brackets can be included or omitted.

Arguments The possible arguments to the rule. If an argument is optional, its default value is provided. Some rules have *subrule* as one of their arguments. In these cases, a list of possible subrules is provided. Some rule arguments allow variables. In these cases, a list of possible variables is provided.

Details Instructions on how to use the rule and on FrameMaker behavior when the rule is not supplied.

XSLT interaction Useful information about the relationship between FrameMaker's Read/Write rules and equivalent XSLT processing.

Examples Various examples of the rule.

See also Cross-references to other relevant information in the manual.

For information on how to create a Read/Write rules file and on the syntax of rules, see [Developer Guide, Chapter 18, Read/Write Rules and Their Syntax](#)

anchored frame

Use the `anchored frame` rule and its subrules to define how FrameMaker handles the content of anchored frames when writing to markup and creating a referenced graphic file. Subrules can specify base entity name, file name construction, graphic file format, notation type and unit of

measure. The rule is used when an anchored frame contains FrameMaker graphics, more than one imported graphic file, or a graphic file that has been copied into the document.

Note: Use the `facet` rule for anchored frames that contain single graphic files that have been imported by reference.

Synopsis and contexts

1. element `"gi"` {
 - is fm graphic element ["`fmtag`"];
 - writer **anchored frame** `subrule`;
 - . . .}
2. element `"gi"` {
 - is fm graphic element ["`fmtag`"];
 - writer **anchored frame** {
 - `subrules`;
 - }
 - . . .}

Arguments

<code>gi</code>	A markup element's name (generic identifier).
<code>fmtag</code>	A FrameMaker element tag.
<code>subrules</code>	An <code>anchored frame</code> rule can have one or more of the following subrules: <ul style="list-style-type: none"> <code>entity name is</code>, tells the software how to create the base name for the entity associated with this element type. <code>export to file</code> tells FrameMaker how to write the file name when it creates a new graphic file, and optionally the graphic format for the file. <code>notation is</code> specifies the data content notation of the entity file. <code>specify size in</code> specifies the units to use when writing the file. <code>export dpi is</code> tells FrameMaker the dpi setting to use for the exported graphic file.

Details

The `anchored frame` rule must be a subrule of a `writer` rule for a graphic element.

On export, if the anchored frame contains only a single imported graphic file, FrameMaker uses that graphic file for the resulting markup graphic element by default. If the anchored frame contains more than one graphic file, or has been modified using FrameMaker graphics tools, the software writes out a graphic file to be used. The default format for these graphic files is CGM. The export format can be changed with the `export to file` rule. For more information about

translating anchored frame contents, see [Developer Guide, Chapter 23, Translating Graphics and Equations](#)

Examples

Assume you use the `Graphic` element for all graphic elements. If the graphic contains any single facet, assume the graphic was imported as an entity and you want the default behavior. However, if the author used FrameMaker graphic tools to create the objects in the graphic element, you want the file written in QuickDraw PICT format.

To accomplish all this, use this rule:

```
element "graphic" {
  is fm graphic element;
  writer anchored frame export to file "${docname}.pic"
  as "PICT";
}
```

Assume the FrameMaker document is named `mydoc.fm`. For the first graphic that is not a single facet, the software writes out a graphic file named `mydoc1.pic` in the PICT format.

If the export DTD declares an entity attribute to identify the graphic file with the `graphic` element, the software generates the following entity declaration:

```
<!ENTITY graphic1 SYSTEM "mydoc1.pic" NDATA PICT>
```

The corresponding graphic element in the markup could be:

```
<graphic entity = "graphic1"/>
```

If the export DTD includes only a `file` attribute to associate the graphic file with the `graphic` element, the software uses this filename as its value:

```
<graphic file = "mydoc1.pic"/>
```

See also

Related rules	"equation" on page 63 "facet" on page 72
Rules mentioned in synopses	"element" on page 54 "is fm equation element" on page 107 "is fm graphic element" on page 109 "writer" on page 160
General information on this topic	Developer Guide, Chapter 23, Translating Graphics and Equations

attribute

Use the `attribute` rule to describe how to process a markup attribute. By default, a markup attribute translates to a FrameMaker attribute of the same name. Usually, this rule occurs as a subrule of the `element` rule, to describe treatment of the attribute `attr` within the element `gi`.

Synopsis and contexts

1. [*mdv*] **attribute** "attr" { . . .
 subrule;
 . . . }
2. element "gi" { . . .
 [*mdv*] **attribute** "attr" { . . .
 subrule;
 . . . }
 . . . }

Arguments

mdv

An optional markup declared value, specifying the type of the markup attribute. Legal values for an XML application are:

- `cdata`
- `nmtoken`
- `nmtokens`
- `entity`
- `entities`
- `id`
- `idref`
- `idrefs`
- `notation`
- `group`.

Legal values for an SGML application are:

- `cdata`
- `name`
- `names`
- `nmtoken`
- `nmtokens`

- number
- numbers
- nutoken
- nutokens
- entity
- entities
- notation
- id
- idref
- idrefs
- group.

attr The name of a markup attribute.

gi A markup element's name (generic identifier).

subrule An attribute rule can have one of the following subrules:

`drop` discards the attribute. If this rule is used, no other attribute subrules may be used.

or:

`is fm attribute` translates a markup attribute into a FrameMaker attribute.

or:

`is fm property` translates a markup attribute to a FrameMaker property such as the width of columns in a table. This subrule is applicable only to cross-reference, marker, graphic, equation, table, and table part elements.

An attribute rule can also have the following subrules:

`implied value is` specifies the value to use for an impliable attribute for which no value is given in a document instance.

`value` translates one of the possible values of a markup name token, `group` or a notation attribute to a specific token of a FrameMaker choice attribute.

Details

- In some cases, the same attribute may occur in several markup elements and may require the same treatment for most of those occurrences. In these situations, you can use the

attribute rule at the highest level to set the default treatment of the attribute. You can then override the default in individual element rules.

- If the `drop` rule is used no other subrules of `attribute` may be used. The subrules `is fm attribute`, and `is fm property` are mutually exclusive. That is, if you use one of these rules, you cannot use the other rule.

Examples

- The following rule specifies that the `sec` attribute of the markup `list` element is in a name token group and corresponds to the attribute `Security` on the corresponding FrameMaker element:

```
element "list"
  group attribute "sec"
  is fm attribute "Security";
```

- Assume you have several elements that represent graphic objects. Each of them has an attribute `w`, representing the width of the object. Use this rule to make the width be 3 inches unless otherwise specified for a particular element:

```
attribute "w" {
  is fm property width;
  implied value is "3in";
}
```

- Assume you have an element `team` with an attribute `color`. The possible values for `color` are `r`, `b`, and `g`. To change the names of these values in the corresponding FrameMaker choice attribute, use this rule:

```
element "team" {
  attribute "color" {
    value "r" is fm value "Red";
    value "b" is fm value "Blue";
    value "g" is fm value "Green";
  }
}
```

See also

Related rules	“fm attribute” on page 74 “is fm attribute” on page 100
Rules mentioned in synopses	“element” on page 54
General information on this topic	Developer Guide, Chapter 20, Translating Elements and Their Attributes

character map

Use the `character map` rule to define mappings between characters in the markup and FrameMaker character sets. Many characters can be expressed using a string; others require using the appropriate integer character code.

Note: XML: This read/write rule is primarily for SGML. XML can use UNICODE characters which makes this rule unnecessary. By default FrameMaker assumes UTF-8 encoding for XML import and export. If you want to use ISOLatin encoding with an XML document, then you may need to use this rule to map characters.

Synopsis and contexts

1. `character map` is `cmap1 [, . . . , cmapn]`;
2. reader `character map` is `cmap1 [, . . . , cmapn]`;
3. writer `character map` is `cmap1 [, . . . , cmapn]`;

Arguments

`cmapi` A mapping between the character set used in the markup document and the FrameMaker character set. Each `cmapi` has one of the following forms:

```
sgmlch = fmch;
sgmlch = trap;
trap = fmch;
```

`sgmlch` is either a 1-character string or a character code representing a character in the markup character set. `sgmlch` can be a single character only if that character has the same character code in both the FrameMaker and markup character sets. Otherwise, you must use the integer character code.

`fmch` is either a 1-character string or a character code representing a character in the FrameMaker character set.

For information on how to represent character codes and special characters in strings, see [Developer Guide, page 276: Strings and constants](#).

Details

- Some characters might be defined in only one of the two character sets. The keyword `trap` is provided for this situation. By default, FrameMaker discards trapped characters.
- The character map need not be a one-to-one mapping. If a character in the input document is mapped to multiple characters in the output character set, FrameMaker uses the output character from the *last* mapping to appear in the `character map` rule.

- If you use the `character map` rule at the highest level, do not also use it inside either a `reader` rule or a `writer` rule. If you use this rule inside a `reader` rule or a `writer` rule and also use it at the highest level, FrameMaker ignores the highest-level `character map` rule. You can only have one occurrence of this rule at the highest level.

Similarly, the `character map` rule can appear in one `reader` rule and one `writer` rule at most. The software ignores any subsequent uses of the `character map` rule.

- If you use the `character map` rule at the highest level, its behavior is bidirectional. For example, you could have this rule:

```
character map is 0x20 = 0x12;
```

This rule specifies that the ISO Latin-1 space character (character code 0x20) maps to the FrameMaker thin space character (character code 0x12). With this rule, FrameMaker translates a thin space to a standard space when it writes a markup document. However, this rule translates *all* spaces in a markup document to thin spaces in a corresponding FrameMaker document. This is unlikely to be the desired behavior. For this reason, instead you should use this rule:

```
reader character map is 0x20 = 0x12;
```

- By default, FrameMaker assumes that the character set your SGML documents use is ISO Latin-1. It provides a default mapping between those character sets. For details, see [Chapter 11, "Character Set Mapping."](#) For information on other character sets you can use, see [Chapter 10, "ISO Public Entities."](#)
- By default, on export FrameMaker produces a character in the SGML document for most printing characters in the corresponding FrameMaker document. FrameMaker documents occasionally include unusual characters that serve no purpose outside FrameMaker. For example, the codes 0x01 and 0x03 are nonprinting characters that represent information about the insertion point movement. On export FrameMaker traps such characters, so that they don't appear in an exported SGML document.
Similarly, on import FrameMaker produces a character in the FrameMaker document for most printing characters. It traps all control characters other than a tab or newline character.
- FrameMaker has an 8-bit character set. The SGML declaration can specify any character set that the SGML parser can handle. Part of the character set description in the SGML declaration is not human-readable and may not be interpretable automatically, therefore, any differences between the native FrameMaker character set and the character set in the SGML document must be specified with the `character map` rule.
- By default, FrameMaker discards trapped characters. You can provide a structure API client to change the processing of trapped characters. For information on creating a structure API client, see the *Structure Import/Export API Programmer's Guide*.

Examples

- Both the FrameMaker and default SGML character sets have a character code for the character ó (lowercase o with an acute accent). In FrameMaker, the character code is 0x97; in the default

SGML character set, the character code is 0xF3. If you want to trap the SGML character that looks like ó, you might try using this rule:

```
character map is "ó" = trap;
```

However, because you enter your read/write rules in a FrameMaker document, FrameMaker interprets that rule as:

```
character map is 0x97 = trap;
```

which is not the behavior you want. Instead, you should use this rule:

```
character map is 0xF3 = trap;
```

- By default, FrameMaker maps the SGML broken bar character to the FrameMaker solid bar character |. The rule for doing so could be written in the following equivalent ways:

```
character map is 0xA6 = "|";  
character map is 0xA6 = 0x7C;  
character map is "\xA6" = "\x7C";
```

- To trap the SGML broken bar character, use this rule:

```
character map is 0xA6 = trap;
```

See also

- For information on the FrameMaker character set, see the FrameMaker Character Sets guide.
- For details of the default mapping between the FrameMaker and ISO Latin-1 character sets, see [Chapter 11, "Character Set Mapping."](#)

convert referenced graphics

Use the `convert referenced graphics` rule to force the software to write out a graphic file when exporting a graphic element that uses a referenced graphic. By default, FrameMaker does not write out graphic files in this case. It is usually more advantageous to simply reference the same graphic file in both the markup and the FrameMaker document. However, you can use this rule to convert all such graphic files to a specific format.

Synopsis and contexts

```
element "gi" { . . .  
    writer facet "facetname" convert referenced graphics;  
    . . . }
```

Arguments

There are no arguments for this rule

Details

- This rule must be a subrule of a facet rule for a graphic element.

- By default, if a graphic or equation element is imported by reference, the software does not create a new graphic file for the element when exporting a FrameMaker document. You can change that behavior using this rule.

Examples

- Assume you want to convert imported graphic files in `graphic` elements which have not been edited in the FrameMaker document, to the PICT format. With the following example, the software would create PICT files for each of these graphic elements:

```
element "graphic" {
  is fm graphic element;

  writer {
    facet default {
      convert referenced graphics;
      export to file "${entity}.pic" as "PICT";
    }
  }
}
```

- For graphic elements with a single TIFF facet, the following example converts the graphic files in the graphic element to PICT:

```
element "graphic" {
  is fm graphic element;
  writer facet "TIFF" {
    convert referenced graphics;
    export to file "${entity}.pic" as
      "PICT";
  }
}
```

See also

Related rules [“facet” on page 72](#)
 [“export to file” on page 67](#)
 [“writer” on page 160](#)

General information [Developer Guide, page 365: Translating Graphics and Equations on this topic](#)

do not include dtd

See [“include dtd” on page 94](#).

do not include sgml declaration

See “include sgml declaration” on page 96.

do not output book processing instructions

See “output book processing instructions” on page 139.

drop

Use the `drop` rule to indicate information that you want discarded. Examples of information you might discard include a markup element or attribute that has no counterpart in FrameMaker, or a FrameMaker non-element marker that has no counterpart in markup.

Synopsis and contexts

1. attribute `"attr"` **drop**;
2. element `"gi"` **drop**;
3. element `"gi"` { . . .
 attribute `"attr"` **drop**;
 . . . }
4. external data entity reference **drop**;
5. fm attribute `"attr"` **drop**;
6. fm element `"fmtag"` **drop**;
7. fm marker `type1` [, . . . , `typen`] **drop**;
8. fm variable **drop**;
9. processing instruction **drop**;

Arguments

<i>attr</i>	The name of a markup or FrameMaker attribute. Note that <code>fm</code> attribute names are case-sensitive and should appear as in the EDD. The case of SGML attribute names depends on the setting of <code>NAMECASE</code> in the <code>SGML.dcl</code> file—For XML attribute names are case sensitive.
<i>gi</i>	A markup element’s name (generic identifier).
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.
<i>type_i</i>	A FrameMaker marker type, such as Index or Type 22.

Details

- When FrameMaker encounters something to be discarded, it makes no attempt to insert the corresponding information into the document it is creating. In the case of a dropped element, it also discards all descendant elements.
- When creating an EDD from a DTD or schema, or a DTD from an EDD, FrameMaker does not generate an element definition corresponding to a dropped element. It also removes any references to the specified element in content rules for other elements unless you've specified a `preserve fm element definition` rule for those elements.
- You can write a structure API client or XSLT stylesheet to process dropped information. Your solution must also handle retrieving discarded information if it is needed when the document is written back to its original format.
- If you use the `drop` rule in a rule, you can use no other subrules of the same rule. For example, you cannot specify that FrameMaker both drop an attribute and translate it to a FrameMaker property with the `is fm property` rule.

XSLT interaction

XSLT allows precise, context based equivalent processing to the FrameMaker `drop` rule. For consistency and maintainability try to avoid mixing the methods used to drop FrameMaker or XML elements.

Examples

- A markup element used instead of a processing instruction to indicate that a page or line break is desired may be discarded when the markup document is read. Text formatting rules in the EDD can be used to indicate a page break in FrameMaker; there is no need to mark the break with an element. To drop the markup element `break`, use this rule:

```
element "break" drop;
```

- By default, FrameMaker stores processing instructions that it does not recognize in non-element markers. In this way, even though FrameMaker does not perform special processing on the processing instruction, when you save the FrameMaker document back to markup, the software writes out the processing instruction so that a different application can use it. If you don't need to write out the processing instructions, you could use this rule:

```
processing instruction drop;
```

See also

- Related rules
- ["drop content" on page 53](#)
 - ["unwrap" on page 154](#)
 - ["preserve fm element definition" on page 140](#)

Rules mentioned in synopses	"attribute" on page 44 "element" on page 54 "external data entity reference" on page 69 "fm attribute" on page 74 "fm element" on page 75 "fm marker" on page 76 "fm variable" on page 87 "processing instruction" on page 143
General information on this topic	Developer Guide, Chapter 20, Translating Elements and Their Attributes

drop content

Use the `drop content` rule to either create a FrameMaker empty element or a markup element with no content from occurrences of *gi*.

Synopsis and contexts

- ```
1. element "gi" {
 is fm element "fmtag";
 reader drop content;
}
```
- ```
2. element "gi" {  
    is fm element "fm tag";  
    writer drop content;  
}
```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

- You can use this rule when you have an element whose content is created in a system-specific way. If you plan to rely on some system to create the content, the existing content at the time you import or export a document may not be relevant. For example, you may have a markup element intended to contain a chapter number. In FrameMaker, you use FrameMaker's formatting capabilities to have the system maintain the value. When reading in the markup document, you can drop the current content of the number element.

- Use `drop content` inside a `reader` rule when you translate markup documents to FrameMaker documents. Use it inside a `writer` rule when you translate FrameMaker documents to markup.

XSLT interaction

XSLT allows precise, context based equivalent processing to the FrameMaker `drop content` rule. For consistency and maintainability try to avoid mixing the methods used to drop content.

Examples

- Assume your DTD has a `toc` element that represents the table of contents for a markup document. FrameMaker can automatically generate a table of contents, which means that this markup element can have its contents dropped upon import.

```
element "toc" reader drop content;
```

- Assume the `total` element's content is computed by a structure API client. Outside the FrameMaker environment you will use a different program to perform the computation. Consequently, you do not want the value that is current when the document is exported. To discard the current value, use this rule:

```
element "total" writer drop content;
```

See also

Related rules	"drop" on page 51 "unwrap" on page 154
Rules mentioned in synopses	"element" on page 54 "reader" on page 145 "writer" on page 160
General information on this topic	Developer Guide, Chapter 20, Translating Elements and Their Attributes Structure Import/Export API Programmer's Guide

element

You use the `element` rule as the primary rule for translating between a markup element and its corresponding FrameMaker representation.

Synopsis and contexts

1. **element** `"gi"` { . . .
 `subrule;`
 . . . }

```
2. element "gi" { . . .
    transform;
    subrule;
    . . . }
```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>transform</i>	<p>The <code>element</code> rule can include a single <code>transform</code> subrule is used to map to a FrameMaker object element.</p> <p><code>is fm colspec</code> specifies that the element represents a CALS table <code>colspec</code>. This subrule applies only to CALS tables.</p> <p><code>is fm cross-reference element</code> specifies that the element corresponds to a FrameMaker cross-reference element.</p> <p><code>is fm element</code> translates the element to a particular FrameMaker element. You use this subrule to rename the element.</p> <p><code>is fm equation element</code> specifies that the element corresponds to a FrameMaker equation element.</p> <p><code>is fm footnote element</code> specifies that the element corresponds to a FrameMaker footnote element.</p> <p><code>is fm graphic element</code> specifies that the element corresponds to a FrameMaker graphic element.</p> <p><code>is fm marker element</code> specifies that the element corresponds to a FrameMaker marker element.</p> <p><code>is fm spanspec</code> specifies that the element represents a CALS table <code>spanspec</code>. This subrule applies only to CALS tables.</p> <p><code>is fm system variable element</code> specifies that the element corresponds to a FrameMaker system variable element.</p> <p><code>is fm table element</code> specifies that the element corresponds to a FrameMaker table element.</p> <p><code>is fm table part element</code> specifies that the element corresponds to a FrameMaker element for a particular table part, such as a table title or cell.</p>
<i>subrule</i>	<p>The subrules of <code>element</code> indicate the treatment of the markup element and its attributes.</p> <p><code>attribute</code> specifies what to do with a markup element's attributes.</p> <p><code>drop</code> discards the element.</p>

`fm attribute` specifies what to do with attributes present in the FrameMaker representation of the element but not in the markup representation of it.

`fm property` specifies what to do with FrameMaker properties associated with the element. This subrule applies only to elements that correspond to graphic, equation, table, table part, cross-reference, or marker elements.

`marker text is` specifies whether the text of a FrameMaker marker element should be element content or an attribute value in markup. This subrule applies only to marker elements.

`drop content` specifies that the content but not the structure of an element should be discarded on import of a markup document.

`end vertical straddle` indicates that the associated table cell or row element terminates a vertical table straddle. This subrule applies only to table cell or row elements.

`insert table part element` indicates that the software should insert the specified table part (title, heading or footing), even if the markup element structure does not contain the corresponding element. This subrule applies only to table elements.

`line break` determines whether to interpret line breaks in text segments in elements in the markup document as forced returns or spaces within the elements.

`start new row` indicates that the occurrence of the associated table cell element always starts a new row in the table. This subrule applies only to table cell elements.

`start vertical straddle` indicates that the associated table cell element starts a vertical table straddle. This subrule applies only to table cell elements.

`unwrap` indicates that the content of the element, but not the element itself, should be included in the translated document.

`anchored frame` tells FrameMaker what to do with graphic elements other than those with a single non-internal FrameMaker facet. This subrule applies only to graphic elements.

`drop content` specifies that the content but not the structure of an element should be discarded on export of a FrameMaker document.

`writer equation` tells FrameMaker what to do with equation elements. This subrule applies only to equation elements.

writer [facet](#) tells FrameMaker what to do with a graphic element that has a single non-internal FrameMaker facet. This subrule applies only to graphic elements.

writer [line break](#) limits the length of lines the software generates in the markup document.

writer [notation is](#) specifies a notation name when the element is a graphic or equation.

writer [specify size in](#) specifies the units of measure for the size of a graphic or equation element.

Details

If you use either the `drop` or `unwrap` subrule of an `element` rule, that subrule must be the element's only subrule. For example, you cannot both `unwrap` a markup element and translate it to a FrameMaker element.

Examples

- To translate the markup element `p` to the FrameMaker element `Paragraph`, use this rule:
- To translate the markup element `tab2` to a FrameMaker table element `Two Table` with two columns, use this rule:

```
element "p" is fm element "Paragraph";
```

```
element "tab2" {  
    is fm table element "Two Table";  
    fm property columns value is "2";  
}
```

See also

Related rules ["fm element" on page 75](#)

General information [Developer Guide, Chapter 20, Translating Elements and Their Attributes on this topic](#)

end vertical straddle

Use the `end vertical straddle` rule inside the `element` rule for a table row or table cell to specify that the row (or the row containing the cell) indicates the end of a vertical straddle

started by some earlier table cell element. The straddle can end either before the current row or at the current row.

Synopsis and contexts

```
element "gi" {
    is fm table row_or_cell element ["fmtag"];
    reader end vertical straddle "name1" [, . . . "namen"]
    [before this row];
    . . .}
```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>row_or_cell</i>	One of the keywords: <code>row</code> or <code>cell</code> .
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.
<i>name_i</i>	A name associated with a table straddle. Each <i>name_i</i> must occur in a corresponding <code>start vertical straddle</code> rule.

Details

- Your DTD may contain elements that you want to format as tables in FrameMaker even though the element hierarchy does not match that required by FrameMaker for tables. In such a situation, the nature of the element hierarchy may indicate where vertical straddles begin and end. The `end vertical straddle` rule allows you to specify such elements.
- Use this rule in conjunction with the `start vertical straddle` rule. That rule specifies a table cell that indicates the first cell in a vertical straddle. In the `start vertical straddle` rule, give a name to the particular straddle started by that element. In the `end vertical straddle` rule, you must specify by name which vertical straddles started by earlier cells are ended by the occurrence of *gi*.
- If you use this rule for a table cell element, you can end only one vertical straddle. If you use it for a table row element, you can end more than one vertical straddle.
- If you use this element without the `before this row` keyword phrase, the cell or row (*gi*) specified in the rule becomes part of the straddle. If you do include that keyword phrase, then the straddle ends in the row above the one specified.

Examples

For an example of the use of this rule, see [“Creating vertical straddles” on page 358](#).

See also

Related rules [“start vertical straddle” on page 152](#)

General information [Developer Guide, Chapter 22, Translating Tables](#)
on this topic

entity

You use the `entity` rule to translate an entity to an appropriate FrameMaker representation. With this rule, you can translate an entity to a particular character or set of characters, a reference element, a text inset, or a FrameMaker variable. If you choose to translate the entity to a text inset, you can also specify how to format that text inset in the resulting document.

Synopsis and contexts

1. `entity "ename" {`
`type_rule;`
`[format_rule;]`
`. . .}`
2. reader `entity "ename" {`
`type_rule;`
`[format_rule;]`
`. . .}`

Arguments

<i>ename</i>	An entity name.
<i>type_rule</i>	One of the following: <code>is fm char</code> translates the entity to a particular character in FrameMaker. <code>is fm reference element</code> translates the entity to an element whose content resides on a reference page in the FrameMaker document. <code>is fm text inset</code> translates the entity to a FrameMaker text inset. <code>is fm variable</code> translates the entity to a FrameMaker non-element variable.
<i>format_rule</i>	One of the following subrules can be specified, but only if <i>type_rule</i> is <code>is fm text inset</code> : <code>reformat as plain text</code> specifies that the software remove the internal structure and formatting from the text of the text inset and apply the formatting used at the insertion point. <code>reformat using target document catalogs</code> specifies that the software retain the text inset's internal structure and apply the containing document's formats and element format rules to the text. This rule is

applied as if the following three options were checked when a file is imported through the File>ImportFile menu: 1. Reformat Using Target Document's catalog; 2. While importing Remove: Manual Page Breaks; and 3. While Importing Remove: Other Format Overrides. For more information, see the section "Import text" in Chapter 9 of the Using FrameMaker guide.

`retain source document formatting` specifies that the software remove the internal structure of the text inset and retain the formatting of the text inset as it appeared in the source document.

Details

- If you use the `entity` rule at the highest level, then it applies both on import and export. If you use it inside a `reader` rule, then FrameMaker translates the entity as specified when importing a markup document, but does not create an entity reference on export.
- For SGML, while you can use this rule to translate any entity type to a text inset, we recommend you convert only `SDATA` entities to text insets. Note that the source file for such a text inset must be a format FrameMaker can automatically filter. Also, such a text inset cannot use a markup document as the source file.
- For XML and SGML, FrameMaker imports external text entities as text insets by default. The source files for these insets can be markup or text files. The software stores entity information on the Entity Declarations reference page so it can export the text inset as an external text entity.
- For XML, `SDATA` and `CDATA` entities are not allowed.

Examples

- To translate the text entity `mn` to the FrameMaker variable `Manual Name`, use this rule:

```
entity "mn" is fm variable "Manual Name";
```

Suppose the text entity `mn` is declared as `<!ENTITY mn "Developer's Guide">`, and the template for the application does not contain a variable named `Manual Name`. Then the software will create a FrameMaker variable named `Manual Name` defined as `Developer's Guide` and replace the reference in the text with the variable text `Developer's Guide`.

However, if a FrameMaker variable named `Manual Name`, defined for example as `My Favorite Manual`, currently exists in the template for the application, when importing SGML, the software will not create a new variable nor modify the existing one. It will replace the reference in the text with the variable text `My Favorite Manual`. When importing XML, it does modify the variable definition.

- To have FrameMaker create a text inset for the `legalese` entity using the text in the file `legal.fm` and to have the software format that text inset as it appears in `legal.doc`, use this rule:

```
entity "legalese" {
    is fm text inset "legal.fm";
    retain source document formatting;
}
```

See also

General information on this topic [Developer Guide, Chapter 21, Translating Entities and Processing Instructions](#)

[Developer Guide, Chapter 25, Translating Variables and System Variable Elements](#)

entity name is

Use the `entity name is` rule only in an `element` rule for a graphic or equation element to provide information the software needs when writing a document containing graphics or equations to markup. The `entity name is` rule determines the name FrameMaker gives an entity reference it generates for the graphic or equation.

Synopsis and contexts

1.

```
element "gi" {
    is fm equation element ["fmtag"];
    writer equation entity name is "ename";
    . . .}}
```
2.

```
element "gi" {
    is fm graphic element ["fmtag"];
    writer anchored frame entity name is "ename";
    . . .}}
```
3.

```
element "gi" {
    is fm graphic element ["fmtag"];
    writer facet "facetname" entity name is "ename";
    . . .}}
```

Arguments

- | | |
|--------------------|--|
| <code>gi</code> | A markup element's name (generic identifier). |
| <code>fmtag</code> | A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD. |

<i>facetname</i>	A facet name. The string for the facetname must exactly match the string for the facetname in the FrameMaker document. To determine a graphic file's facetname, select the graphic, click Graphics>ObjectProperties, and observe the facetname in the dialog box.
<i>ename</i>	A string representing the base name for an entity name.

Details

By default, when FrameMaker exports an external data entity for a graphic or equation, it uses the entity name that is stored with the graphic inset. If there is no such entity name, the software generates a name for the entity based on the element name. You use the `entity name is` rule to change this behavior.

The entity name you specify is a base name FrameMaker uses to generate a unique entity name. When it needs to create a new entity name, FrameMaker adds an integer to the name specified by *ename* to create a unique name.

If the keyword `facet` is used, the rule applies to a graphic element that contains only a single facet with the name specified by *facetname*. This occurs when the graphic element is an anchored frame containing only a single imported graphic object whose original file was in the *facetname* graphic format. You can use this rule multiple times if you want FrameMaker to treat several file formats differently.

Examples

- Assume you have a markup element `graphic` that corresponds to graphic elements in FrameMaker. Suppose further that some of the graphic elements in FrameMaker contain imported-by-copy graphics, or contain modifications to a graphic inset using FrameMaker graphic tools, or contain just graphic objects drawn using FrameMaker graphic tools. On export, the software must create new graphic files for these elements and declare entities for them. By default, FrameMaker would declare entities for these graphic elements based on the element name "graphic," for example, `graphic1`, `graphic2`, and so on. To specify that the names of the entities associated with such successive graphic elements have the form `car1`, `car2`, and so on, use this rule:

```
element "graphic" {
  is fm graphic element;
  writer anchored frame entity name is "car";
}
```

- Assume with a single facet graphics in the `car` element sometimes use the IGES file format and sometimes use the TIFF file format. Also assume that the DTD for the application does not currently contain entity declarations for the imported-by-reference graphic files. By default, the software would declare entities for all such graphics based on the element name "car," for

example, `car1`, `car2`, and so on. If you want to name the entities for the IGES graphics `icar` and the entities for the TIFF graphics `tcar`, then use this rule:

```
element "car" {
    is fm graphic element;
    writer facet "IGES" entity name is "icar";
    writer facet "TIFF" entity name is "tcar";
}
```

See also

Related rules	"export to file" on page 67 "notation is" on page 137 "specify size in" on page 149
Rules mentioned in synopses	"element" on page 54 "is fm graphic element" on page 109 "is fm equation element" on page 107 "anchored frame" on page 41 "equation" on page 63 "facet" on page 72 "writer" on page 160
General information on this topic	Developer Guide, Chapter 23, Translating Graphics and Equations

equation

Use the `equation` rule only in an `element` rule for an equation element, to provide information the software needs when writing to markup a document containing equations. FrameMaker creates graphic files to represent equations. Use this rule to specify information about the files FrameMaker creates for instances of the equation element. By default, the software creates a file in CGM format for each equation, and the filename is based on the element name. Also, by default, if the equation element is associated with an external data entity, then the entity name is based on the element name.

Synopsis and contexts

```
element "gi" {
    is fm equation element ["fmtag"];
    writer equation subrule;
    . . .}
```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.
<i>subrule</i>	<p>An equation rule can have the following subrules:</p> <p><code>entity name is</code> tells the software how to create the base name for the entity associated with this element type.</p> <p><code>export to file</code> tells the software to write a new file for the associated external data entity.</p> <p><code>notation is</code> specifies the data content notation of the entity file.</p> <p><code>specify size in</code> specifies the units to use when writing the file.</p>

Examples

Assume you have an element named `math` with an attribute of type `Entity` that is mapped to the `fm property entity` for this element. If you want to create TIFF files for the equations in a document named `mytest.doc`, you might use this rule:

```

element "math" {
    is fm equation element;
    writer equation export to file "$(docname).eqn" as "TIFF";
}

```

The software will create graphic files for each equation in `mytest.doc` named `mytest1`, `mytest2`,...and will declare entities named `math1`, `math2`, ...for each graphic.

See also

Related rules	<p>“anchored frame” on page 41</p> <p>“facet” on page 72</p> <p>“is fm graphic element” on page 109</p>
Rules mentioned in synopses	<p>“element” on page 54</p> <p>“is fm equation element” on page 107</p> <p>“writer” on page 160</p>
General information on this topic	Developer Guide, Chapter 23, Translating Graphics and Equations

export dpi is

You use the `export dpi` rule only in an `element` rule for a graphic or equation element, to provide information the software needs when writing a document containing graphics or

equations to markup. The `export dpi` rule tells FrameMaker the dpi setting to use for an exported graphic file.

Synopsis and contexts

1. element "gi" {


```

        is fm equation element ["fmtag"];
        writer equation
          export dpi is number;
          . . .
      . . .}
```
2. element "gi" {


```

        is fm graphic element ["fmtag"];
        writer anchored frame
          export dpi is number;
          . . .
      . . .}
```
3. element "gi" {


```

        is fm graphic element ["fmtag"];
        writer facet "facetname"
          export dpi is number;
          . . .
      . . .}
```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.
<i>facetname</i>	A facet name. The string for the facetname must exactly match the string for the facetname in the FrameMaker document. To determine a graphic file's facetname, select the graphic, click Graphics>ObjectProperties, and observe the facetname in the dialog box.
<i>number</i>	The required dpi value.

Details

- In the absence of this rule, FrameMaker uses the dpi setting associated with the graphic file. If there is no setting associated with the graphic, the software assumes a value of 300.
- In Windows, if the initialization file for a graphics filter specifies a dpi setting that setting overrides this rule whenever that filter is used to export a graphic file.
- If the keyword `facet` is used, the rule applies to a graphic element that contains only a single facet with the name specified by *facetname*. This occurs when the graphic element is an

anchored frame containing only a single imported graphic object whose original file was in the *facetname* graphic format. You can use this rule multiple times if you want FrameMaker to treat several file formats differently.

Examples

- Assume you export the FrameMaker file `Math.doc` and have the following rule:

```
element "eqn" {
  is fm equation element "Equation";
  writer equation
    export dpi is 72;
}
```

When FrameMaker finds an instance of the `Equation` element, it exports equations as graphic files at 72 dpi.

- Assume you have the rule:

```
element "imp" {
  is fm graphic element;
  writer facet "TIFF" {
    convert referenced graphics;
    export dpi is 1200;
    export to file "${entity}.tif";
  }}
}
```

This rule tells FrameMaker for every graphic element with a single TIFF facet, it should write a new graphic file with a dpi of 1200, using the entity name as part of the graphic file's filename.

See also

Related rules	"convert referenced graphics" on page 49 "entity name is" on page 61 "notation is" on page 137 "specify size in" on page 149
Rules mentioned in synopses	"element" on page 54 "is fm graphic element" on page 109 "is fm equation element" on page 107 "anchored frame" on page 41 "equation" on page 63 "facet" on page 72 "writer" on page 160
General information on this topic	Developer Guide, Chapter 23, Translating Graphics and Equations

export to file

You use the `export to file` rule only in an `element` rule for a graphic or equation element, to provide information the software needs when writing a document containing graphics or equations to markup. The `export to file` rule tells FrameMaker how to write the file name when it creates a new graphic file, and optionally the graphic format for the file.

Synopsis and contexts

1. `element "gi" {
 is fm equation element ["fmtag"];
 writer equation
 export to file "fname" [as "format"];
 . . .}`
2. `element "gi" {
 is fm graphic element ["fmtag"];
 writer anchored frame
 export to file "fname" [as "format"];
 . . .}`
3. `element "gi" {
 is fm graphic element ["fmtag"];
 writer facet "facetname"
 export to file "fname" [as "format"];
 . . .}`

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.
<i>facetname</i>	A facet name. The string for the facetname must exactly match the string for the facetname in the FrameMaker document. To determine a graphic file's facetname, select the graphic, click Graphics>ObjectProperties, and observe the facetname in the dialog box.
<i>fname</i>	A base filename which can be either absolute or relative to the output directory. Note: If path information is included in <i>fname</i> , use double backslashes to translate path backslashes correctly. The <i>fname</i> argument can contain the variables <code>\$(docname)</code> and <code>\$(entity)</code> , described below.
<i>format</i>	A file data content format code, such as TIFF or PICT. See Developer Guide, Chapter 23, Translating Graphics and Equations for a complete list of graphic format codes. <i>format</i> must be one of these code names.

Details

- By default, if a graphic element has a single facet (other than a FrameMaker internal facet) that was imported by reference, FrameMaker does not create a new graphic file. On export, the original file will be associated with a markup graphic element via the `file` attribute, or via the `entity` attribute plus a corresponding entity declaration. You can use the `convert referenced graphics` rule to force FrameMaker to export such graphic files.
- If the keyword `facet` is used, the rule applies to a graphic element that contains only a single facet with the name specified by `facetname`. This occurs when the graphic element is an anchored frame containing only a single imported graphic object whose original file was in the `facetname` graphic format. In this case, the rule is only executed if the `convert referenced graphics` rule is also used. Otherwise, it is ignored. You can use this rule multiple times if you want FrameMaker to treat several file formats differently.
- If your rules specify the software will write a graphic file, if a graphic element has a single facet (other than a FrameMaker internal facet), FrameMaker writes the graphic file in that format by default. It writes the graphic file for equation elements and all other graphic elements in CGM format by default.

If you supply a `format` argument, you must first make sure that the format is one known to FrameMaker. For information on which graphic export filters the software provides and on how to add new ones, see [Developer Guide, Chapter 23, Translating Graphics and Equations](#).

- The `fname` argument can use these variables:

Variable	Meaning
<code>\$(entity)</code>	The value of the corresponding markup element's <code>entity</code> attribute. If the source of the graphic inset wasn't originally an entity, this variable defaults to a unique name based on the name of the element. You can change this name using the <code>entity name is</code> rule.
<code>\$(docname)</code>	The name of the FrameMaker file, excluding any extension or directory information.

- The `fname` argument is used as a template for the actual filename FrameMaker generates for a particular graphic or equation element. FrameMaker takes the filename specified with the `fname` argument and may append an integer to the filename to ensure uniqueness of the filename. For an example of this behavior, see the first example below.

Examples

- Assume you export the FrameMaker file `Math.fm` and have the following rule:

```

element "eqn" {
    is fm equation element "Equation";
    writer equation
        export to file "$(docname).eqn" as "PICT";
}

```


When FrameMaker finds an instance of the `Equation` element, it generates filenames of the form `MathN.eqn` until it finds a name that does not collide with an already existing file. For example, if you already have files in the specified directory named `Math1.eqn` and `Math2.eqn`, the software writes the first equation to a file named `Math3.eqn`. FrameMaker writes the equation file in PICT format, instead of the default CGM format.

- Assume you have the rule:

```
element "imp" {
  is fm graphic element;
  writer facet "TIFF" {
    convert referenced graphics;
    export to file "${entity}.tif";
  }
}
```

This rule tells FrameMaker that if it encounters a graphic element with an imported graphic file with a single TIFF facet, it should write that graphic to the file specified by `$(entity).tif`.

See also

Related rules	“convert referenced graphics” on page 49 “entity name is” on page 61 “notation is” on page 137 “specify size in” on page 149
Rules mentioned in synopses	“element” on page 54 “is fm graphic element” on page 109 “is fm equation element” on page 107 “anchored frame” on page 41 “equation” on page 63 “facet” on page 72 “writer” on page 160
General information on this topic	Developer Guide, Chapter 23, Translating Graphics and Equations

external data entity reference

Use the `external data entity reference` rule to drop references to all external data entities. By default, FrameMaker stores such references as the marker text in non-element Entity Reference markers.

Synopsis and contexts

```
external data entity reference drop;
```

ArgumentsNone.**Details**

- In markup, the values of general entity name attributes, such as those used with graphics, are not considered entity references. This rule does not affect how FrameMaker treats general entity name attributes. In XML such entity name attributes are the only way to reference non-parsed entities such as graphics.
- When you translate a markup document to FrameMaker, when the software encounters an external data entity reference such as:

```
&door;
```

it stores the reference as the text of a non-element DOC Entity Reference marker by default, with the following marker text:

```
door
```

When you translate a FrameMaker document to markup, it outputs the marker text of non-element DOC Entity Reference markers as entity references.

Examples

To discard all external data entity references, use this rule:

```
external data entity reference drop;
```

See also

Rules mentioned in [“drop” on page 51](#)
synopses

General information [Developer Guide, Chapter 21, Translating Entities and Processing](#)
on this topic [Instructions](#)

external dtd

Use this rule to specify how an exported markup instance refers to the current structure application's DTD. By default, FrameMaker uses the name of the file containing the DTD as the system identifier in the external identifier for the DTD. The `external dtd` rule provides the software with a different external identifier. The different forms of the rule allow specification of a system identifier, public identifier, or both.

Synopsis and contexts

1. writer **external dtd** is system;
2. writer **external dtd** is system "sysid";
3. writer **external dtd** is public "pubid";

```
4. writer external dtd is public "pubid" "sysid";
```

Arguments

sysid A system identifier.

pubid A public identifier.

Details

- Use this rule when you export FrameMaker documents to markup documents. To use this rule, you must have a DTD specified for the current structure application in the `structapps.fm` file.
- By default, FrameMaker does not reproduce the DTD in the document type declaration subset. Instead, it uses the filename of the DTD that was specified in the structure application to write a document type declaration of the form:

```
<!DOCTYPE doctype SYSTEM "fname" [ . . .
```

where *doctype* is the document type name and *fname* is the DTD filename specified in the structure application. This rule allows you to specify different system and public identifiers.

- To output both external DTD and Schema with an XML document, use this rule and specify a Schema file for output in the XML structure application (in `structapps.fm`). This rule modifies how the external DTD is written.

To output Schema only, with no DTD, specify only the Schema file, not the DTD, in `structapps.fm`. You do not need to use this rule.

- You cannot use the `external dtd` rule in the same read/write rules file as the `include dtd` rule.

Examples

- To specify a local DTD as an external DTD and include the path with the filename, you could use this rule:

```
writer
  external dtd is
    system "/doc/dtds/manuals.dtd";
```

Note that the Windows platform requires two backslashes in paths in the rules file in order to translate as one backslash.

- To specify and locate the CALS DTD as an external DTD, you could use this rule:

```
writer external dtd is
  public "-//USA-DOD//DTD MIL-M-38784B//EN"
  "/doc/dtds/cals.dtd";
```

- To specify just the CALS DTD as an external DTD using a public identifier, you could use this rule:

```
writer external dtd is
    public "-//USA-DOD//DTD MIL-M-38784B//EN" ;
```

You could then specify the location of the DTD in the structure application using the `EntitiesLocation` element. A DTD is an entity in the strictest sense.

See also

Related rules	“include dtd” on page 94 “include sgml declaration” on page 96 “write structured document” on page 159 “write structured document instance only” on page 159
Rules mentioned in synopses	“writer” on page 160

facet

Use the `facet` rule only in an `element` rule for a graphic element, to provide information the software needs when writing a document containing graphics to markup. The `facet` rule applies only when a graphic element is an anchored frame containing only a single imported graphic object whose original file was in the `facetname` graphic format. Use this rule to specify information about the graphic file and/or entity declaration for instances of the graphic element.

Synopsis and contexts

```
element "gi" {
    is fm graphic element ["fmtag"];
    writer facet "facetname" subrule;
    . . .}
```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.
<i>facetname</i>	The name of the particular facet to which this rule applies, or “default” for all facets.
<i>subrule</i>	<p>A <code>facet</code> rule can have the following subrules:</p> <pre>convert referenced graphics</pre> <p>tells the software to create new graphic files for imported graphic files with a single facet.</p>

`entity name is` tells the software how to create the base name for the entity associated with this element type.

`export to file` tells the software the name to use for graphics it creates, and optionally, the graphic format to which it should convert.

`notation is` specifies the data content notation of the entity.

`specify size in` specifies the units to use when writing the file.

Details

To specify all facets, use the keyword `default` for the `facetname` argument. For example:

```
element "pict" {
  is fm graphic element "Picture";
  writer {
    facet default {
      convert referenced graphics;
      export to file "${entity}.tif" as "TIFF";
      . . .
    }
  }
}
```

will convert every imported graphic file in the document to a TIFF file, no matter what its original facet was.

Examples

By default, FrameMaker does not create a new graphic file for a graphic element that originated as an external entity, and was not modified by the user in any way. Assume you want the software to generate a graphic file for every imported TIFF file, whether it was modified or not. Then you could use this rule:

```
element "pict" {
  is fm graphic element "Picture";
  writer {
    facet "TIFF" {
      convert referenced graphics;
      export to file "${entity}.tif" as "TIFF";
    }
  }
}
```

See also

Related rules

- [“anchored frame” on page 41](#)
- [“convert referenced graphics” on page 49](#)
- [“equation” on page 63](#)

Rules mentioned in synopses	“element” on page 54 “is fm equation element” on page 107 “is fm graphic element” on page 109 “writer” on page 160
General information on this topic	Developer Guide, Chapter 23, Translating Graphics and Equations

fm attribute

You use the `fm attribute` rule with the “drop” subrule to discard an attribute that you’ve defined for a FrameMaker element but that does not exist on the corresponding markup element. Read/write rules do not support double-byte characters, so you cannot use this rule to drop attributes with double-byte characters in their names.

Synopsis and contexts

1. `fm attribute "attr" drop;`
2. `element "gi" { . . .
 fm attribute "attr" drop;
 . . . }`

Arguments

<code>attr</code>	A FrameMaker attribute name.
<code>gi</code>	A markup element’s name (generic identifier).

Examples

- Assume the element `chapter` exists in both the markup and FrameMaker representations of your documents. In FrameMaker, you use the `XRefLabel` attribute in formatting cross-references to this element. Since this attribute exists only for formatting purposes, you don’t want it in the markup document. To drop this attribute on export, use this rule:

```
element "chapter" {  
    is fm element;  
    fm attribute "XRefLabel" drop;  
}
```

- If you use the `XRefLabel` attribute on many elements for the same purpose, you can discard it from all elements on export with this rule:

```
fm attribute "XRefLabel" drop;
```

- If you want to keep the `XRefLabel` attribute on the `appendix` element, but drop it from all others, use these rules:

```
element "appendix" {
    is fm element;
    attribute "xreflab" is fm attribute "XRefLabel";
}
fm attribute "XRefLabel" drop;
```

Note that the order of these rules is not important. If you reversed them, the `XRefLabel` attribute would still be correctly interpreted for the `appendix` element, since that reference to the attribute is more specific. Note also that case is sensitive for fm attribute names.

See also

Related rules	"attribute" on page 44 "is fm attribute" on page 100
Rules mentioned in synopses	"element" on page 54 "drop" on page 51
General information on this topic	Developer Guide, Chapter 20, Translating Elements and Their Attributes

fm element

Use the `fm element` rule to tell FrameMaker what to do on export with FrameMaker elements that do not correspond to markup elements. Read/write rules do not support double-byte characters, so you cannot use this rule to process elements with double-byte characters in their names.

Synopsis and contexts

1. `fm element "fmtag" drop;`
2. `fm element "fmtag" unwrap;`

Arguments

fmtag A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

- Use this rule when you export FrameMaker documents to markup documents.
- If you use this rule, you may want to write a structure API client to handle the export of the element or to create it on import.

- The first version of this rule discards the FrameMaker element on export. The second version inserts the contents of *fmtag* in the corresponding markup document, but not *fmtag* itself.
- If you use this rule to unwrap FrameMaker cross-reference elements or system variable elements, those elements become text in the resulting markup document.

XSLT interaction

XSLT allows precise, context based equivalent processing to the FrameMaker `drop` and `unwrap` rules. For consistency and maintainability try to avoid mixing the methods used to drop or unwrap FrameMaker elements.

Examples

- If `Chapter Number` is a FrameMaker element that you want to discard on export, use this rule:

```
fm element "Chapter Number" drop;
```

If you use this rule and want to create this element on import, you need to write a structure API client.

- If `Modification Date` is a FrameMaker system variable element that you wish to translate to text on export to markup, use this rule:

```
fm element "Modification Date" unwrap;
```

See also

Related rules [“element” on page 54](#)
 [“is fm element” on page 106](#)

Rules mentioned in [“drop” on page 51](#)
synopses [“unwrap” on page 154](#)

General information [Developer Guide, Chapter 20, Translating Elements and Their Attributes on this topic](#)

fm marker

On export, you use the `fm marker` rule to tell FrameMaker what to do with non-element markers other than markers of the type reserved for storing processing instructions, PI entities, and external data entities. (By default, Structure PI markers are reserved for processing instructions, and Entity Reference markers are reserved for external data entities.) In the absence of a rule to the contrary, the software creates processing instructions for non-element markers.

You can also choose to discard them. Read/write rules do not support double-byte characters, so you cannot use this rule to process markers with double-byte characters in their names.

Synopsis and contexts

```
fm marker ["type1", . . . , "typen"] drop;  
fm marker ["type1", . . . , "typen"] is processing instruction;
```

Arguments

type_i The name of a FrameMaker marker type.

Details

- If *type_i* is specified, this rule applies only to markers of that type. If no *type_i* is specified, this rule applies to all non-element markers other than markers of the reserved type. For information on what the software does with the reserved marker type, see [Developer Guide, Chapter 26, Translating Markers](#)
- You can have multiple occurrences of this rule in a rules file, to determine different treatment for different FrameMaker markers. You can have only one occurrence of the rule with no explicitly listed markers. A given marker type can be explicitly mentioned in only one occurrence of this rule.
- The order of `fm marker` rules is not important. A more specific occurrence of the rule always takes precedence over a more general occurrence. For example, the following rules:

```
fm marker "Index" is processing instruction;  
fm marker drop;
```

have the same effect, exporting only index markers as processing instructions, if they occur in this order:

```
fm marker drop;  
fm marker "Index" is processing instruction;
```

XSLT interaction

XSLT allows precise, context based equivalent processing to the FrameMaker `drop` rule. For consistency and maintainability try to avoid mixing the methods used to drop FrameMaker non-element markers.

Examples

- To discard all non-element markers, use this rule:

```
fm marker drop;
```
- To discard non-element conditional text markers but retain all others as processing instructions, use this rule:

```
fm marker "Conditional Text" drop;
```

- To retain only Index and Hypertext markers as processing instructions and drop all other non-element markers, use the following set of rules:

```
fm marker "Index", "Hypertext" is processing instruction;
fm marker drop;
```

See also

Related rules	“is fm marker element” on page 111
Rules mentioned in synopses	“drop” on page 51 “is processing instruction” on page 134
General information on this topic	Developer Guide, Chapter 26, Translating Markers

fm property

You use the `fm property` rule to determine values for properties defined for certain types of FrameMaker constructs that you do not want to represent as markup attributes.

Synopsis and contexts

1. Cross-reference elements

```
element "gi" {
  is fm cross-reference element ["fmtag"];
  fm property cross-reference format value is val;
  . . .}
```

1.1 Arguments

val A valid cross-reference format name. These names are case-sensitive and must appear in the rule the same as in the structure application's template.

2. Graphic or equation elements

```
element "gi" {
  is fm graphic_or_equation element ["fmtag"];
  fm property prop value is "val";
  . . .}
```

2.1 Arguments

prop

- `alignment` Indicates the anchored frame's horizontal alignment on the page.

val

- `aleft` Align left

- `acenter` Align center
- `aright` Align right
- `ainside` Align inside, or closest to the binding margin.
- `aoutside` Align outside, or farthest from the binding margin.
- `angle` Indicates an angle of rotation for the anchored frame that contains the graphic. You must specify exact multiples of 90 degrees. Otherwise, the value is ignored and the graphic is imported at 0 degrees (default).
val examples:
 - 0 No rotation (default)
 - 90 Rotate 90 degrees clockwise
 - -90 Rotate 90 degrees anticlockwise
 - 180 Rotate 180 degrees
 - 270 Rotate 270 degrees.
- `baseline offset` Indicates how far from the baseline of a paragraph to place an anchored frame. Baseline offset is relevant only for anchored frames whose `position` attribute is one of `inline`, `sleft`, `sright`, `snear`, or `sfar`.
val A number plus a valid unit of measure, e.g. "12pt", "10mm". If not supplied, the value is 0.
- `cropped` Indicates whether a wide graphic should be allowed to extend past the margins of the text frame. The `cropped` property is relevant only for anchored frames whose `position` attribute is one of `top`, `below`, or `bottom`.
val
 - 0 The graphic may extend past the margins of the text frame.
 - 1 (Default) The graphic is cropped at the margins of the text frame.
- `dpi` Indicates how to scale an imported graphic object.
val The value of the `dpi` attribute must be an integer greater than 0. If not supplied, the default value is 72.
- `entity` Provides the entity name of the imported graphic. This rule limits the graphic import to a single, fixed file for all instances of the element.
val A valid entity name as defined in an entity declaration in the markup instance.
- `file` Provides the file name of the imported graphic. This rule limits the graphic import to a single, fixed file for the element.
val A valid file name for an imported graphic.

- `floating` Indicates whether the graphic should be allowed to float from the paragraph to which it is attached. The `floating` property is relevant only for anchored frames whose `position` property is one of `top`, `below`, or `bottom`.

val

- 0 (Default) No float, the graphic must stay with the paragraph.
- 1 Allow float.

- `height` Indicates the height of the anchored frame.

val The value for a single imported graphic object is the sum of the height of the object plus twice the value of the vertical offset property.

- `horizontal offset` Indicates how far the graphic object is offset from the right and left edges of the anchored frame.

val A number with a valid unit of measure. If not supplied, the default value is 6.0pt.

- `import angle` Indicates an angle of rotation in degrees for the graphic inside its anchored frame.

val A real number, if not supplied, the default value is 0.0.

- `import by reference or copy` Indicates whether an imported graphic object remains in a separate file or is copied into the FrameMaker document on import from markup.

val

- `ref` (Default) The object is referenced and will not be copied into the document.
- `copy` The object will be copied into the document.

- `import size` indicates the size of the imported graphic object by specifying a width and height.

val Two numbers, separated by a space, with a valid units of measure. The first measurement is the width and the second is the height. If no unit of measure is supplied, points are assumed. Example: "100mm 50mm".

- `near-side offset` Indicates how far to set a frame from the text frame to which the frame is anchored. It is relevant only for anchored frames whose `position` attribute is one of `sleft`, `sright`, `snear`, or `sfar`.

val A number plus a valid unit of measure, e.g. "12pt", "10mm". If not supplied, the value is 0.

- `position` Indicates where on the page to put the anchored frame. If not supplied, the value is `below`.

val Possible anchoring position values are as follows:

- `inline` At insertion point.
- `top` At top of column.
- `below` Below current line.
- `bottom` At bottom of column.
- `sleft` Outside column - left side.
- `sright` Outside column - right side.
- `snear` Outside column - right side.
- `sfar` Outside column - side closer to the page edge.
- `sinside` Outside column - side closer to the binding.
- `soutside` Outside column - side farther from the binding.
- `tleft` Outside text frame - left side.
- `tright` Outside text frame - right side.
- `tnear` Outside text frame - side closer to the page edge.
- `tfar` Outside text frame - side farther from the page edge.
- `tinside` Outside text frame - side closer to the binding.
- `toutside` Outside text frame - side closer to the binding.
- `runin` Run into paragraph.

- `sideways` Indicates that the imported graphic will be flipped left to right to give a mirror image.

val

- 0 (Default) No flip.
- 1 Flip left/right.

- `vertical offset` Indicates how far the graphic object is offset from the top and bottom edges of the anchored frame.

val A number plus a valid unit of measure. If not supplied, the default value is 6.0pt.

- `width` Indicates the width of the anchored frame.

val The value for a single imported graphic object is the sum of the width of the object plus twice the value of the horizontal offset property.

3. Marker elements

```
element "gi" {
    is fm marker element ["fmtag"];
    fm property prop value is val;
    . . .}
```

3.1 Arguments

- prop*
- `marker text` Provides a fixed text string for all instances of the marker.
val Any valid marker text string.
 - `marker type` Identifies the type of marker if not provided by a markup attribute.
val A valid marker type name.

4. Table elements

```
element "gi" {  
  is fm table element ["fmtag"];  
  fm property prop value is val;  
  . . .}
```

4.1 Arguments

- prop*
- `column ruling` Specifies whether all columns should have ruling on their right side. This property does not specify the style or weight of the ruling. The default ruling is defined by the relevant table format in the structured template.
val
 - 0 Columns have no ruling.
 - 1 Columns have ruling.
 - `column widths` The width of successive columns in the table. On import from markup these widths are reapplied regardless of any changes made by the user.
val Each value is either an absolute width or a width proportional to the size of the entire table. If proportional widths are used, the `pgwide` attribute or `page wide` property determines the table overall width. Example for a three column table:
"22mm 40mm 100mm".
 - `columns` The number of columns in the table. This is essential to the correct rendering of the table if the markup does not state the number of columns as an attribute value.
val An integer greater than 0.
 - `page wide` This is relevant only to tables whose columns use proportional widths on pages with more than a single column. In this case, the attribute indicates whether the entire table should be the width of the column in which it is anchored, or the width of the overall text frame.
val

- 0 (Default) The table is the width of the text column.
- 1 The table is the width of the text frame.
- `row_ruling` Specifies whether all rows should have ruling on their bottom side. This property does not specify the style or weight of the ruling. The default ruling is defined by the relevant table format in the structured template.

val

- 0 Rows have no ruling.
- 1 Rows have ruling.
- `table_border_ruling` Specifies whether the table should have ruling around its outside borders. This property does not specify the style or weight of the ruling. The default ruling is defined by the relevant table format in the structured template.

val

- `all` Rows have no ruling.
- `top` Rows have ruling.
- `table_format` Specifies the table format for all instances of the FrameMaker table element.

val A name of a table format that is present in the application's structured template.

5. Table cell elements

```
element "gi" {
    is fm table cell element ["fmtag"];
    fm property prop value is val;
    . . .}
```

5.1 Arguments

prop

- `column_name` Associates a name with a cell in a given column.
val A valid column name as defined in a colspec.
- `column_number` Indicates the column number that the cell will start in. This rule is used when the column number is not available in the markup and requires each cell in a given row to have a unique element name.
val An integer greater than 0.
- `column_ruling` Specifies whether the cell should have ruling on its right side. This property does not specify the style or weight of the ruling. The default ruling is defined by the relevant table format in the structured template.

val

- 0 Cell has no right side ruling.
- 1 Cell has right side ruling.

- `end column name` Specifies the name of a column that ends a straddle.

val A valid column name as defined in a colspec.

- `horizontal straddle` Specifies the number of columns a straddled cell spans.

val An integer greater than 1 and no greater than the number of columns.

- `more rows` Specifies the number of additional rows a straddled cell spans.

val An integer greater than 1 and no greater than the number of rows in the table part. The total number of rows the cell occupies is `more rows+1`.

- `rotate` Indicates how much to rotate the contents of a cell.

val The CALS model restricts this property to a boolean value, where 1 indicates a rotation of 90 degrees anti-clockwise. FrameMaker extends the possible values to allow rotations of 0, 90, 180, and 270 degrees.

- `row ruling` Specifies whether the cell should have ruling on its bottom side. This property does not specify the style or weight of the ruling. The default ruling is defined by the relevant table format in the structured template.

val

- 0 Cell has no bottom side ruling.
- 1 Cell has bottom side ruling.

- `span name` Applies a predefined CALS spanspec, starting at this cell.

val A valid spanspec name.

- `start column name` Specifies the name of a column that begins a horizontal straddle.

val A valid column name as defined in a colspec.

- `vertical straddle` Specifies the number of rows a straddled cell spans.

val An integer greater than 1 and no greater than the number of rows in the section (head, body or foot) of the table that contains the starting cell.

6. Table row elements

```
element "gi" {
    is fm table row element ["fntag"];
    fm property prop value is val;
    . . .}
```

6.1 Arguments

- prop*
- **maximum height** Specifies the maximum height for each row in the table.
val A number plus a valid unit of measure, e.g. "24pt", "15mm". If not supplied, the maximum height of the row is not limited.
 - **minimum height** Specifies the minimum height for each row in the table.
val A number plus a valid unit of measure, e.g. "12pt", "9mm". If not supplied, the minimum height of the row is not limited.
 - **row type** Sets the row type.
val
 - heading
 - body
 - footing
 - **row ruling** Specifies whether the cell should have ruling on its bottom side. This property does not specify the style or weight of the ruling. The default ruling is defined by the relevant table format in the structured template.
val
 - 0 Cell has no bottom side ruling.
 - 1 Cell has bottom side ruling.

7. For CALS table colspecs:

```
element "gi" {
    is fm colspec;
    fm property prop value is val;
    . . .}
```

7.1 Arguments

- prop*
- cell alignment character
 - cell alignment offset
 - cell alignment type
 - column name

- column number
- column ruling
- column width
- row ruling
- vertical alignment

```
8. element "gi" {
    is fm spanspec;
    fm property prop value is val;
    . . .}
```

8.1 Arguments

- prop*
- cell alignment character
 - cell alignment offset
 - cell alignment type
 - column ruling
 - end column name
 - row ruling
 - span name
 - start column name
 - vertical alignment

9. Used at the top level

```
fm property prop value is "val";
```

9.1 Arguments

gi A markup element's name (generic identifier).

fmtag A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

- This rule applies only to an element corresponding to a cross-reference, graphic, equation, marker, table, or table part element.
- Some FrameMaker properties have no natural markup counterparts. If you choose to not translate such properties as markup attributes, a markup document will not contain information on appropriate values for these properties. In this situation, you can use the `fm property` rule to explicitly set property values when reading a markup document.

- This rule can be used either at the highest level to set a default or within an `element` rule to specify the translation of a property for a particular element.
- If you use this rule to set a property value explicitly, you cannot also have a markup attribute that corresponds to this property. For example, the following rule is erroneous:

```
element "tab2" {
    is fm table element;
    attribute "w" is fm property column widths;
    fm property column widths value is "1in 2in";
}
```

Examples

- To translate the markup element `table` to a FrameMaker table with two columns:

```
element "table" {
    is fm table element;
    fm property columns value is "2";
}
```

On import to FrameMaker, the software creates the table as a 2-column table in FrameMaker.

- Assume you have a markup element `halfpage` that holds a 4.5 inch by 6.5 inch graphic object; it does not use an attribute to store the size information. You can translate this to a FrameMaker graphic as follows:

```
element "halfpage" {
    is fm graphic element;
    fm property width value is "6.5";
    fm property height value is "4.5";
}
```

See also

Related rules	“is fm property” on page 112 “is fm property value” on page 119
General information on this topic	Developer Guide, Chapter 22, Translating Tables Developer Guide, Chapter 23, Translating Graphics and Equations Developer Guide, Chapter 24, Translating Cross-References Developer Guide, Chapter 26, Translating Markers

fm variable

On export, use the `fm variable` rule to tell FrameMaker what to do with certain variables. Use this rule if you do not want them translated to entities. Read/write rules do not support double-

byte characters, so you cannot use this rule to process variables with double-byte characters in their names.

Synopsis and contexts

```
fm variable ["var1", . . . , "varn"] drop;
```

Arguments

var_i The name of a FrameMaker variable.

Details

- Use this rule when you export FrameMaker documents to markup documents. It applies only to non-element variables, not to system variable elements.
- If *var_i* is specified, this rule applies only to that variable. If no *var_i* is specified, this rule applies to all variables.
- If you use this rule, you may want to write a structure API client, or use an XSLT transform to handle the export of variables or to create variables on import.
- You can have multiple occurrences of this rule in a rules document to determine different treatment for different FrameMaker variables. You can have only one occurrence of the rule with no explicitly listed variables. A given variable can be explicitly mentioned in only one occurrence of this rule.

Examples

To translate the FrameMaker variables `Licensor` and `Product` as entities and discard all other variables, use these rules:

```
entity "licensor" is fm variable;  
entity "product" is fm variable;  
fm variable drop;
```

See also

Related rules [“is fm system variable element” on page 125](#)

General information on this topic [Developer Guide, Chapter 21, Translating Entities and Processing Instructions](#)
[Developer Guide, Chapter 25, Translating Variables and System Variable Elements](#)
[Structure Import/Export API Programmer’s Guide](#)

fm version

The `fm version` rule specifies the version of the product being run. It is required and must be the first rule in all rules documents. If you create your rules document with the New Read/Write Rules command, this rule automatically appears in the document.

Synopsis and contexts

```
fm version is "8.0";
```

ArgumentsNone.

Details

Note that you would use the string "8.0" in this rule even though the product version may be an incremental release above 8.0, such as 8.0.1.

See also

General information [Developer Guide, Chapter 18, Read/Write Rules and Their Syntax](#) on this topic

generate book

Use the `generate book` subrule of a highest-level `reader` rule to specify whether FrameMaker should use elements or processing instructions to indicate where in a markup document to start a book and its components in the corresponding FrameMaker book.

Synopsis and contexts

1. `reader generate book`
 `use processing instructions;`
2. `reader generate book`
 {
 `put element "gi1" in file ["fname1"];`
 `. . .`
 `put element "giM" in file ["fnameM"];`
 }
3. `reader generate book` [for doctype "`dt1`" [, . . . "`dtN`"]]
 {
 `put element "gi1" in file ["fname1"];`
 `. . .`
 `put element "giM" in file ["fnameM"];`
 }

Arguments

<i>dt_i</i>	A document type name.
<i>gi_j</i>	A generic identifier.
<i>fname_j</i>	A filename for the book component. FrameMaker adds a counter to the name (before the suffix if there is one) as needed, to generate a unique filename. You can use the <code>\$(bookname)</code> variable to base the component's filename on the book filename (excluding any suffix). If you do not supply this argument, the filename is <i>gi_j.doc</i> .

Details

- By default, when reading a markup document into FrameMaker, the software uses the `<?FM book ?>` and `<?FM document ?>` processing instructions to indicate the start of a book and of its components. The following rule confirms this default behavior:

```
reader generate book
  use processing instructions;
```

- Your DTD may be defined so that you can use elements to indicate the start of a book and its components. When you use the second form of the `generate book` rule, FrameMaker creates a book for every markup document you translate. When you use the third form of the `generate book` rule, it creates a book only for markup documents whose DTD specifies the document type you've listed in the rule. If you have a markup document with a different document type, FrameMaker translates that document as a single FrameMaker document, even if it contains elements referenced in `put element` rules. For example, assume you have this rule:

```
reader generate book for doctype "manual"
  put element "chapter" in file;
```

If you translate a markup document whose highest-level element is `report`, that document becomes a single FrameMaker document, even if it contains `chapter` descendant elements.

- When it encounters one of the *gi_j* elements specified in a `put element` subrule, FrameMaker starts a new book component. Since the software does not allow an element to be broken across files, it places the entire *gi_j* element in the same file, even if another element appears that you've said should start a new file. To illustrate, assume the `section` element can occur either within or outside of a `chapter` element and you have this rule:

```
reader generate book {
  put element "chapter" in file;
  put element "section" in file;
}
```

When FrameMaker encounters a `chapter` element, it starts a new file. If it encounters a `section` element as a child of that `chapter` element, it does not start a new file. It continues with the file started by the `chapter` element. On the other hand, if the software encounters a `section` element outside a `chapter` element it does start a new file for it.

- Consider these points when dividing a markup document into book components:

- Every FrameMaker document must contain exactly one highest-level element. That is, there cannot be two elements in a single file that do not have an ancestor element in the same file.
- A book element can contain substructure but cannot directly contain text. That is, child elements that can contain text must occur in separate files.

Assume you have this rule:

```
reader generate book
    put element "chapter" in file;
```

And you have a markup document with the following element structure:

```
<manual>
  <chapter>
    <head>Introduction</head>
    . . .
  </chapter>
  <appendix>
    <head>The final word</head>
    . . .
  </appendix>
</manual>
```

When FrameMaker translates this document, it creates a book with `manual` as the highest-level element in the book file. When it encounters the `chapter` element, the software starts a new file for that element. When it encounters the `appendix` element, FrameMaker flags an error, because your rules have not told it what to do with this element. It cannot put the element in the same file as the preceding `chapter` element, because that would create two highest-level elements in the same file. It also cannot put the `appendix` element in the book file, because it contains text.

- By default, when it writes a FrameMaker book to markup, the software writes `<?FM book ?>` and `<?FM document ?>` processing instructions for the book and book components. It does this even if you use the `generate book` rule to have particular elements specify book components when reading a markup document. If you do not want FrameMaker to output these processing instructions, use `writer do not output book processing instructions`.

Examples

- If you know that a markup document should always correspond to a FrameMaker book and that individual files in the book should start when the document reaches a `toc` or `chapter` element, you can use this rule:

```
reader generate book {
    put element "toc" in file;
    put element "chapter" in file "ch.doc";
}
```

With this rule, FrameMaker creates a book for each markup document. In a markup document, FrameMaker starts a new book component when it encounters a `toc` or `chapter` element. For the first `toc` element, FrameMaker uses the filename `toc1` unless a file of that name already exists in the directory it is using. It continues that book component until it encounters either another `toc` element or a `chapter` element. At that point, it starts a new book component. It tries to put the first `chapter` element in a file called `ch1.doc`.

- Assume that a markup document whose highest-level element is either `manual` or `book` should correspond to a FrameMaker book and any other markup document should correspond to an individual FrameMaker document. Further assume that the books created from `manual` and `book` elements should have new files for each instance of the elements `chapter`, `front`, or `toc`. To accomplish all this, you can use this rule:

```
reader generate book for doctype "manual", "book"
{
  put element "chapter" in file "ch.doc";
  put element "front" in file;
  put element "toc" in file "${bookname}.toc";
}
```

With this rule, FrameMaker asks you for a name for the book file if you open a markup document with `manual` as its document type. If you specify `myfile.book` as its name, and the document contains two `chapter` elements, one `front` element, and one `toc` element, FrameMaker creates the following files: `myfile.book`, `ch1.doc`, `ch2.doc`, `front`, and `myfile.toc`.

See also

Related rules [“output book processing instructions” on page 139](#)

General information [Developer Guide, Chapter 28, Processing Multiple Files as Books on this topic](#)

implied value is

Use the `implied value is` rule to specify default attribute values in your EDD to correspond with imported elements that specify no value for the attribute. For example, assume your DTD declares an element named `list`, which has an attribute named `style` defined as `<!ATTLIST list style (bul | num) #IMPLIED>`. For importing the DTD, you can use this rule to set up a default value in the EDD for the `Style` attribute of the `List` element. Then, if you import a `list` element that has no value for `style`, this default attribute value will be used

for formatting purposes. Also, when you export the EDD, the DTD will declare the `style` attribute for the `list` element as `#IMPLIED`.

Synopsis and contexts

1. attribute "attr" { . . .
 implied value is "val";
 . . . }
2. element "gi" { . . .
 attribute "attr" { . . .
 implied value is "val";
 . . . } . . . }

Arguments

<i>attr</i>	The name of an impliable attribute in markup.
<i>val</i>	A value to use for the <i>attr</i> attribute.
<i>gi</i>	A markup element's name (generic identifier).

Details

- This rule is for importing DTDs and exporting EDDs. In FrameMaker, a default attribute value can only be specified in the EDD, so this rule has no effect when importing a markup instance or exporting a FrameMaker document.
- This rule specifically does not supply an attribute value for an element that has no value in the markup instance. It only sets up a default attribute value in the EDD. This default value can be used for formatting by attributes. When you export the document, FrameMaker will not add a value for the attribute to the element's start tag.
- The rule can be used in a highest-level `attribute` rule to specify the value to use for that attribute in any element. Alternatively, it can be used in an `attribute` rule within an `element` rule to specify the value for that element only.

Examples

Assume you have these declarations for a markup element used for cross-references:

```
<!ELEMENT xref EMPTY>
<!ATTLIST xref
    id IDREF #IMPLIED
    format CDATA #IMPLIED>
```

And you have this rule:

```
element "xref" {
  is fm cross-reference element;
  attribute "format" {
    is fm property cross-reference format;
    implied value is "Page";
  }
}
```

When FrameMaker encounters an instance of the `xref` element in a markup document and that instance does not have a value for the `format` attribute, the software use the Page cross-reference format for the cross-reference in the FrameMaker document.

See also

Related rules	"value" on page 157
Rules mentioned in synopses	"attribute" on page 44 "element" on page 54
General information on this topic	Developer Guide, Chapter 20, Translating Elements and Their Attributes "Default value" on page 196

include dtd

By default, when creating a markup document, FrameMaker includes in the document type definition an external identifier that refers to the DTD file. Therefore, it does not include a copy of actual declarations in the document type declaration subset. The `include dtd` rule tells FrameMaker to do so.

Synopsis and contexts

```
writer [do not] include dtd;
```

ArgumentsNone.

Details

- You use this rule when you export FrameMaker documents to markup documents. If this rule is specified, FrameMaker does not generate an external identifier in the `DOCTYPE` declaration.
- To confirm the default behavior, you can use the opposite rule:

```
writer do not include dtd;
```

- The `include dtd` rule and the `external dtd` rule are mutually exclusive. That is, you cannot use both of these rules in the same read/write rules file. (If you try to put both of these rules in the same file, you will get an alert.) Also, the `include dtd` rule and the `write structure document instance only` rule are mutually exclusive.

- To write an entire markup document, including a DTD and (for SGML) an SGML declaration with the document instance, you must use the following rules:

```
writer {  
    include sgml declaration;  
    include dtd;  
}
```

- This rule uses the DTD that is specified in the current structure application. If that DTD includes references to external files, this rule does not expand those references as it writes out the DTD. Instead, it writes out the references as they appear in the parent DTD file.
- You can use this rule to translate the EDD from the current document as an a DTD that is written in the markup document. To do this, use the `include dtd` rule, but use a structure application that does not specify a DTD in its definition. Be warned that if your document uses the CALS table model, the resulting DTD may be incorrect.
- When you use this rule, no Schema information is included in the output. If you use this rule to output an internal DTD and the XML structure application specifies a Schema file for export, that file is converted to internal DTD (see [Chapter 6, “XML Schema to DTD Mapping”](#)) and that DTD is saved with the markup document.

If the XML structure application specifies both a Schema file and a DTD, the DTD is output as the internal DTD and the Schema is dropped.

If the XML structure application specifies neither a Schema file nor a DTD, an internal DTD is created from the first of these sources that is available:

- an external DTD for the imported document;
- a DTD that is the result of conversion from a Schema in the imported document;
- the element catalog of the template.

Examples

If your document type declarations are in a file called `report.dtd`, then by default FrameMaker includes this document type declaration in the document it creates on export:

```
<!DOCTYPE report SYSTEM "report.dtd" [  
    . . . more declarations specific to this document instance . . .  
>
```

If you specify the `include dtd` rule, then FrameMaker includes this document type declaration in the document it creates:

```
<!DOCTYPE report [  
    . . . declarations specific to this document instance . . .  
    . . . contents of the file, report.dtd . . .  
>
```

See also

- Related rules
- [“external dtd” on page 70](#)
 - [“include sgml declaration,” next](#)
 - [“write structured document” on page 159](#)
 - [“write structured document instance only” on page 159](#)

include sgml declaration

By default, FrameMaker does not include an SGML declaration in a generated SGML document. The `sgml declaration` rule tells FrameMaker to include one. The SGML declaration is copied from the file in the associated application subset. To see the default SGML declaration used by FrameMaker, see [Chapter 9, “SGML Declaration.”](#)

Note: XML: This read/write rule is for SGML-only.

Synopsis and contexts

```
writer [do not] include sgml declaration;
```

ArgumentsNone.

Details

- To confirm the default behavior, you can use the opposite rule:

```
writer do not include sgml declaration;
```
- You cannot use the `include sgml declaration` rule in the same read/write rules file as the `write sgml document instance only` rule. Note that using both rules in the same rules file does not give an error. Also, “write sgml document instance only” takes priority, regardless of order.
- To write an entire SGML document, including an SGML DTD and SGML declaration with the document instance, you must use the following rules:

```
writer {
    include sgml declaration;
    include dtd;
}
```

See also

- Related rules
- [“external dtd” on page 70](#)
 - [“include dtd,” \(the previous section\)](#)
 - [“write structured document” on page 159](#)
 - [“write structured document instance only” on page 159](#)

insert table part element

You use the `insert table part element` rule when creating a FrameMaker table element on import of a markup document. This rule tells FrameMaker to create a table part of the designated type, even if the markup document does not contain content for that table part.

Synopsis and contexts

```
element "gi" { . . .
    is fm table element ["fmtag1"];
    reader insert table part element ["fmtag2"];
. . . }
```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>fmtag₁</i>	A FrameMaker element tag for a table element. These names are case-sensitive and must appear in the rule the same as in the EDD.
<i>part</i>	One of the keywords: <code>title</code> , <code>heading</code> , or <code>footing</code> .
<i>fmtag₂</i>	A FrameMaker element tag for a table part element.

Details

By default, as the last step in creating a table element when reading a markup document, FrameMaker discards parts of the table that have no content, even if the general rule for the element requires that table part. (Your EDD may supply the content, for example, by using format rules that specify a prefix for the element.) If you do not want FrameMaker to remove the table part element with no content, OR if you want FrameMaker to create a table part element for you when the markup instance does not contain this element, use the `insert table part element` rule.

Examples

Assume you have a markup element `statetab`, which you represent as a 3-column table in FrameMaker, with the same table headings everywhere it occurs. You use formatting rules in the EDD to specify the table headings. In this situation, the markup document does not include information that corresponds to the table headings, so you want the software to add the table heading element when reading such a markup instance and drop it when exporting a FrameMaker document to markup. Suppose your DTD has these declarations:

```
<!ELEMENT statetab ((state, pop, income)+)>
<!ELEMENT state (#PCDATA)>
<!ELEMENT pop (#PCDATA)>
<!ELEMENT income (#PCDATA)>
```

and your EDD has these FrameMaker element definitions:

Element (Table): State Table

General rule: State Head, State Body

Text format rules

1. In all contexts.

Use paragraph format: TableCell

Element (Table Heading): State Head

General rule: State Head Row

Text format rules

1. In all contexts.

Default font properties

Weight: Bold

Element (Table Row): State Head Row

General rule: Label

Element (Table Cell): Label

General rule: <EMPTY>

Text format rules

1. If context is: {first}

Numbering properties

Autonumber format: State

Else if context is: {last}

Numbering properties

Autonumber format: Household Income

Else

Numbering properties

Autonumber format: Population

Element (Table Body): State Body

General rule: State Row+

Element (Table Row): State Row

General rule: State, Income, Population

Element (Table Cell): State

General rule: <TEXT>

Element (Table Cell): Income

General rule: <TEXT>

Element (Table Cell): Population

General rule: <TEXT>

Note that the Label element provides the text for the column headings.

You could use these rules:

```
element "statetab" {
  is fm table element "State Table";
  fm property columns value is "3";
  reader insert table heading element "State Head";
}

element "state" {
  is fm table cell element;
  fm property column number value is "1";
  fm property row type value is "Body";
}

element "income" is fm table cell element;

element "pop" is fm table cell element "Population";

fm element "State Head" drop;
fm element "State Body" unwrap;
fm element "State Row" unwrap;
```

To convert the following instance to the desired FrameMaker document:

```
<statetab>
  <state>Georgia</state>
  <pop>15,000,000</pop>
  <income>25,000</income>
  <state>Mississippi</state>
  <pop>8,000,000</pop>
  <income>18,000</income>
</statetab>
```

- The first rule identifies `statetab` as a 3-column table element and tells it to always create a heading element for an occurrence of this `statetab`.
- The second rule identifies `state` as a table cell that must always occur in the first column of a body row. This ensures that FrameMaker starts a new table row whenever it encounters a `state` element.
- The other element rules identify other elements used as table cells. The `fm element drop` rule causes the software to drop the element that was created by FrameMaker per the `insert element` rule so that it does not appear in the markup. Note also that it is necessary for the software to have a `tablerow` element and a `tablebody` element in its table structure. However, these do not appear in the markup document. FrameMaker creates such necessary elements by default. Since they do not correspond to markup elements, they are unwrapped on export to markup—not dropped, because that would lose the contents of the entire table.

See also

General information [Developer Guide, Chapter 22, Translating Tables](#) on this topic

is fm attribute

Use the `is fm attribute` rule to specify that a markup attribute translates to a FrameMaker attribute. The optional parts of this rule allow you to have the software make several changes to the attribute during translation. Read/write rules do not support double-byte characters, so you cannot use this rule to process attributes with double-byte characters in their names.

Synopsis and contexts

1. `[mdv] attribute "attr" { . . .
 is fm [read-only] [fmtype] attribute
 ["fmattr"] [range from low to high];
 . . . }`
2. `element "gi" { . . .
 [mdv] attribute "attr"
 is fm [read-only] [fmtype] attribute
 ["fmattr"] [range from low to high];
 . . . }`

Arguments

mdv An optional markup declared value, specifying the type of the markup attribute. Legal values for an XML application are:

- cdata
- nmtoken
- nmtokens
- entity
- entities
- id
- idref
- idrefs
- notation
- group.

Legal values for an SGML application are:

- `cdata`
- `name`
- `names`
- `nmtoken`
- `nmtokens`
- `number`
- `numbers`
- `nutoken`
- `nutokens`
- `entity`
- `entities`
- `notation`
- `id`
- `idref`
- `idrefs`
- `group`.

attr A markup attribute name.

fmtype A FrameMaker attribute type. Legal values are: String, Strings, Integer, Integers, Real, Reals, UniqueID, IDReference, IDReferences, and Choice.

fmattr A FrameMaker attribute name.

low A number, indicating the low end of a numeric range.

high A number, indicating the high end of a numeric range.

Details

- You can use the `is fm attribute` rule in a highest-level `attribute` rule to specify the translation of that attribute in all elements for which it is defined. Or you can use it in an `attribute` subrule in an `element` rule to specify the translation of the `attribute` in only that element.
- You may want some markup attributes to become FrameMaker properties. If so, you cannot also import them as FrameMaker attributes. For information on the defined FrameMaker properties, see [“is fm property” on page 112](#).
- To specify only that the attribute is an attribute in both representations, use this version:

```
attribute "attr" is fm attribute;
```

- To also rename it during translation, use this version:

```
attribute "attr" is fm attribute "fmattr";
```

- To specify that the FrameMaker attribute is read-only—that is, that an end user cannot change the attribute's value—use this version:

```
attribute "attr" is fm read-only attribute;
```

- To specify that an attribute that takes numeric values can have values only in a particular range, use this version:

```
attribute "attr" is fm attribute range from low to high;
```

- To specify that a markup attribute with a particular declared value translates to a FrameMaker attribute of a type other than the default translation, use this version:

```
mdv attribute "attr" is fm fmtype attribute;
```

- Note that you can use more than one of the optional pieces of the `is fm attribute` rule at the same time. For example, you can both rename an attribute and state that it is read-only by using this version:

```
attribute "attr" is fm read-only attribute "fmattr";
```

Examples

- To translate the markup `sec` attribute to the FrameMaker `SecurityRanking` attribute in all elements in which it occurs, use this rule:

```
attribute "sec" is fm attribute "SecurityRanking";
```

- To translate the markup `sec` attribute to the FrameMaker `SecurityRanking` attribute in most elements in which it occurs, but to change it to the `Section` attribute in the `BookPart` element, use these rules:

```
element "BookPart"  
  attribute "sec" is fm attribute "Section";  
  
attribute "sec" is fm attribute "SecurityRanking";
```

- Assume you have a markup attribute named `perc` with a declared value of `CDATA`, and assume you know that this attribute always has values that are integers in the range from 0 to 100. You can translate the `perc` attribute to the `Percentage` attribute with this rule:

```
CDATA attribute "perc"  
  is fm integer attribute "Percentage" range from 0 to 100;
```

- Assume that a markup element has an attribute with declared value `name` and that the attribute has a defined set of allowable values. You can translate that attribute and some of its possible values with the following rule:

```

element "fish" {
  name attribute "loc" {
    is fm choice attribute "CommonLocation";
    value "micro" is fm value "Micronesia";
    value "galap" is fm value "Galapagos Islands";
    value "png" is fm value "Papua New Guinea";
  }
}

```

See also

Related rules [“fm attribute” on page 74](#)

Rules mentioned in
synopses [“attribute” on page 44](#)
 [“element” on page 54](#)

General information [Developer Guide, Chapter 20, Translating Elements and Their Attributes on this topic](#)

is fm char

For SGML, use the `is fm char` rule to translate an SGML SDATA entity to a single character in FrameMaker. For XML, use this rule to translate an internal entity to a single character in FrameMaker.

Synopsis and contexts

1. `entity "ename" is fm char ch [in "fmchartag"];`
2. `reader entity "ename" is fm char ch [in "fmchartag"];`

Arguments

ename An entity name.

ch A one-character string or a numeric character code (specified using the syntax for an octal, hexadecimal, or decimal number described in [Developer Guide, page 276: Strings and constants](#)). Note that if the desired character is a digit or a white-space character, you must enter it as a numeric character code.

fmchartag A FrameMaker character format tag.

Note that the character format must use a non-standard font family such as Symbol or Zapf Dingbats for this argument to take effect.

Details

- For SGML, instead of using this rule to translate an `SDATA` entity, you can use a parameter literal of a particular form. For information on how to do so, see [Developer Guide, page 326: Translating SDATA entities as special characters in FrameMaker](#).
- For XML, `SDATA` entities are not allowed. This rule translates internal entities to FrameMaker characters, and it translates FrameMaker to internal entities.
- You can use the `is fm char` rule within an `entity` rule at the highest level to have the translation occur in both directions. Or you can put the `entity` rule inside a `reader` rule to have the translation occur only when reading a markup document into FrameMaker. For example, your SGML document might use a `period` entity for entering some instances of the period character in your SGML document. If you use this rule:

```
entity "period" is fm char ".";
```

then the entity references for `period` in the instance are translated correctly to the period character in FrameMaker. But on export, all periods in the document become references to the `period` entity (which is not likely what you had in mind). To have the period entities read correctly when importing an instance, but have periods remain the period character on export, use this version of the rule:

```
reader
  entity "period" is fm char ".";
```

- Without the `in` clause, the software translates the entity using the default character format of the enclosing paragraph element. Frequently, however, special characters require a font change. In these cases, you use the `in` clause.
- For SGML, DTDs frequently use the entity sets defined in Annex D of the SGML Standard, often called ISO public entity sets, for providing commonly used special characters. FrameMaker includes copies of these entity sets and provides rules to handle them for your application. For information on how FrameMaker supports ISO public entities, see [Chapter 10, "ISO Public Entities."](#)

Examples

- To translate the `SDATA` entity `sum` as the mathematical summation sign in the Symbol font (Σ), you could use either of these rules in your rules document:

```
entity "sum" is fm char "S" in "Symbol";
```

```
entity "sum" is fm char "\x53" in "Symbol";
```

```
entity "sum" is fm char 0x53 in "Symbol";
```

If FrameMaker encounters a reference to the `summation` entity when importing a markup document, it replaces the reference with Σ (assuming your FrameMaker template defines the Symbol character format appropriately and the entity is declared in the DTD). If the software encounters Σ when exporting an document, it generates a reference to the `summation` entity

(assuming the Symbol character format is defined appropriately and applied to the character, and that the DTD for your application has an entity declaration for “sum”).

- To translate both the `thin` and `en` internal entity references in an XML instance to `en` spaces in FrameMaker and to write all `en` spaces as an `en` entity reference, use these rules:

```
entity "en" is fm char 0x13;  
reader entity "thin" is fm char 0x13;
```

See also

Rules mentioned in [“entity” on page 59](#)
synopses

General information [Developer Guide, Chapter 21, Translating Entities and Processing Instructions](#)
on this topic

is fm cross-reference element

Use the `is fm cross-reference element` rule to identify a markup element that translates to a cross-reference element in FrameMaker. You can choose either to have the same name in both representations or to change the name during translation. The markup element should have an attribute of type IDREF and declared content of EMPTY. Read/write rules do not support double-byte characters, so you cannot use this rule to process elements with double-byte characters in their names.

Synopsis and contexts

```
element "gi" { . . .  
    is fm cross-reference element ["fmtag"];  
    . . . }
```

Arguments

gi A markup element’s name (generic identifier).

fmtag A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

If you use the `is fm cross-reference element` rule, the other subrules of the `element` rule that you can use for that markup element are as follows:

- `attribute` specifies what to do with a markup element’s attributes.
- `fm attribute` specifies what to do with attributes present in the FrameMaker representation of the element but not in the markup representation.
- `fm property` specifies what to do with FrameMaker properties associated with the element.

- reader [drop content](#) specifies that the content but not the structure of an element should be discarded on import of a markup document.

Examples

- To have the markup element `xref` become the FrameMaker cross-reference element `Xref`, use this rule:

```
element "xref" is fm cross-reference element;
```

- To have it become the FrameMaker cross-reference element `CrossRef`, use this rule:

```
element "xref" is fm cross-reference element "CrossRef";
```

See also

Rules mentioned in [“element” on page 54](#)
synopses

General information [Developer Guide, Chapter 24, Translating Cross-References](#)
on this topic

is fm element

If you do not specify a value for `fmtag`, the `is fm element` rule specifies only that a markup element remains an element in FrameMaker. This is the default behavior. With a value for `fmtag`, this rule changes the element name when it is translated between markup and FrameMaker.

Synopsis and contexts

```
element "gi" { . . .  
    is fm element ["fmtag"];  
    . . . }
```

Arguments

`gi` A markup element's name (generic identifier).

`fmtag` A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

If you use the `is fm element` rule, the other subrules of the `element` rule that you can use for that markup element are as follows:

- [attribute](#) specifies what to do with a markup element's attributes.
- `fm attribute` specifies what to do with attributes present in the FrameMaker representation of the element but not in the markup representation.
- `fm property` specifies what to do with FrameMaker properties associated with the element.

- reader [drop_content](#) specifies that the content but not the structure of an element should be discarded on import of a markup document.
- writer [drop_content](#) specifies that the content but not the structure of an element should be discarded on export of a FrameMaker document.

XSLT interaction

XSLT allows precise, context based control over element renaming. For consistency and maintainability try to avoid mixing the methods used to rename FrameMaker or XML elements.

Examples

To translate the markup element `par` to the FrameMaker element `Paragraph`, use this rule:

```
element "par" is fm element "Paragraph";
```

See also

Rules mentioned in [“element” on page 54](#)
synopses

General information [Developer Guide, Chapter 20, Translating Elements and Their Attributes](#)
on this topic

is fm equation element

Use the `is fm equation element` rule to identify a markup element that translates to an equation element in FrameMaker. You can choose either to have the same name in both representations or to change the name during translation. Read/write rules do not support double-byte characters, so you cannot use this rule to process elements with double-byte characters in their names.

Synopsis and contexts

```
element "gi" { . . .  
    is fm equation element ["fmtag"];  
    . . . }
```

Arguments

- | | |
|--------------|--|
| <i>gi</i> | A markup element's name (generic identifier). |
| <i>fmtag</i> | A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD. |

Details

If you use this rule, the other subrules of the `element` rule that you can use for the same markup element are as follows:

- `attribute` specifies what to do with a markup element's attributes.
- `fm attribute` specifies what to do with attributes present in the FrameMaker representation of the element but not in the markup representation.
- `fm property` specifies what to do with FrameMaker properties associated with the element.
- `writer` [equation](#) tells FrameMaker what to do with equation elements.

XSLT interaction

XSLT is not able to convert markup elements to/from FrameMaker equation elements. However, XSLT allows precise, context based control over element renaming. For consistency and maintainability try to avoid mixing the methods used to rename FrameMaker or XML elements.

Examples

- To have FrameMaker equation element `Eqn` become the markup element `eqn`, use this rule:

```
element "eqn" is fm equation element;
```
- To have FrameMaker equation element `Equation` become the markup element `eqn`, use this rule:

```
element "eqn" is fm equation element "Equation";
```

See also

Related rules ["is fm graphic element" on page 109](#)

Rules mentioned in ["element" on page 54](#)
synopses

General information [Developer Guide, Chapter 23, Translating Graphics and Equations on this topic](#)

is fm footnote element

Use the `is fm footnote element` rule to identify a markup element that translates to a footnote element in FrameMaker. You can choose either to have the same name in both representations or to change the name during translation. Read/write rules do not support double-byte characters, so you cannot use this rule to process elements with double-byte characters in their names.

Synopsis and contexts

```
element "gi" { . . .  
    is fm footnote element ["fmtag"];  
    . . . }
```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

If you use this rule, the other subrules of the `element` rule that you can use for the same markup element are as follows:

- `attribute` specifies what to do with a markup element's attributes.
- `fm attribute` specifies what to do with attributes present in the FrameMaker representation of the element but not in the markup representation.

XSLT interaction

XSLT is not able to convert markup elements to/from FrameMaker footnote elements. However, XSLT allows precise, context based control over element renaming. For consistency and maintainability try to avoid mixing the methods used to rename FrameMaker or XML elements.

Examples

- To translate the markup element `fn` to the `Fn` footnote element in FrameMaker, use this rule:

```
element "fn" is fm footnote element;
```

- To translate it to the `Footnote` footnote element, use this rule:

```
element "fn" is fm footnote element "Footnote";
```

See also

Rules mentioned in ["element" on page 54](#)
synopses

General information [Developer Guide, Chapter 20, Translating Elements and Their Attributes](#)
on this topic

is fm graphic element

Use the `is fm graphic element` rule to identify a markup element that translates to a graphic element in FrameMaker. You can choose either to have the same name in both representations or to change the name during translation. Read/write rules do not support

double-byte characters, so you cannot use this rule to process elements with double-byte characters in their names.

Synopsis and contexts

```
element "gi" { . . .  
    is fm graphic element ["fntag"];  
    . . . }
```

Arguments

- | | |
|--------------|--|
| <i>gi</i> | A markup element's name (generic identifier). |
| <i>fntag</i> | A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD. |

Details

If you use this rule, the other subrules of the `element` rule that you can use for the same markup element are as follows:

- `attribute` specifies what to do with a markup element's attributes.
- `fm attribute` specifies what to do with attributes present in the FrameMaker representation of the element but not in the markup representation.
- `fm property` specifies what to do with FrameMaker properties associated with the element.
- writer [anchored frame](#) tells FrameMaker what to do with graphic elements other than those with a single non-internal FrameMaker facet.
- writer [facet](#) tells FrameMaker what to do with an imported graphic element that has a single non-internal FrameMaker facet.

XSLT interaction

XSLT is not able to convert markup elements to/from FrameMaker graphic elements. However, XSLT allows precise, context based control over element renaming. For consistency and maintainability try to avoid mixing the methods used to rename FrameMaker or XML elements.

Examples

- To translate the markup element `pict` to the `Pict` graphic element in FrameMaker, use this rule:

```
element "pict" is fm graphic element;
```

- To translate it to the `Picture` graphic element, use this rule:

```
element "pict" is fm graphic element "Picture";
```

See also

Related rules ["is fm equation element" on page 107](#)

Rules mentioned in ["element" on page 54](#)
synopses

General information [Developer Guide, Chapter 23, Translating Graphics and Equations](#)
on this topic

is fm marker element

Use the `is fm marker element` rule to identify a markup element that translates to a marker element in FrameMaker. You can choose either to have the same name in both representations or to change the name during translation. Read/write rules do not support double-byte characters, so you cannot use this rule to process elements with double-byte characters in their names.

Synopsis and contexts

```
element "gi" { . . .  
    is fm marker element ["fmtag"];  
    . . . }
```

Arguments

gi A markup element's name (generic identifier).

fmtag A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

If you use this rule, the other subrules of the `element` rule that you can use for the same markup element are as follows:

- [attribute](#) specifies what to do with a markup element's attributes.
- `fm attribute` specifies what to do with attributes present in the FrameMaker representation of the element but not in the markup representation.
- [fm property](#) specifies what to do with FrameMaker properties associated with the element.
- [marker text is](#) specifies whether the text of a FrameMaker marker element should be element content or an attribute value in markup.

XSLT interaction

XSLT is not able to convert markup elements to/from FrameMaker marker elements. However, XSLT allows precise, context based control over element renaming. For consistency and maintainability try to avoid mixing the methods used to rename FrameMaker or XML elements.

Examples

- To translate the markup element `m` to the `M` marker element in FrameMaker, use this rule:

```
element "m" is fm marker element;
```

- To translate it to the `Marker` marker element, use this rule:

```
element "m" is fm marker element "Marker";
```

See also

Related rules ["marker text is" on page 136](#)

["fm marker" on page 76](#)

Rules mentioned in ["element" on page 54](#)
synopses

General information [Developer Guide, Chapter 26, Translating Markers](#)
on this topic

is fm property

Use the `is fm property` rule to translate a markup attribute to a FrameMaker property. This rule can apply in a highest-level `attribute` rule to set a default. Or it can apply within an `element` rule for a table, table part, marker, cross-reference, graphic, or equation element, to set the property only for that element. Read/write rules do not support double-byte characters, so you cannot use this rule to process attributes with double-byte characters in their names.

Synopsis and contexts

```
1. attribute "attr" { . . .  
    is fm property prop;  
    . . . }
```

```
2. element "gi" { . . .  
    attribute "attr" { . . .  
        is fm property prop;  
    . . . } . . . }
```

Arguments

`attr` The name of a markup attribute.

`gi` A markup element's name (generic identifier).

`prop` A FrameMaker property. Possible properties are:

- For cross-reference elements:
 - `cross-reference format`

- `cross-reference id`
- For graphic and equation elements:
 - `alignment` Indicates the anchored frame's horizontal alignment on the page.
 - `angle` Indicates an angle of rotation for the anchored frame that contains the graphic. The markup must specify exact multiples of 90 degrees. Otherwise, the value is ignored and the graphic is imported at 0 degrees which is the default. Examples:
 - 0 No rotation (default).
 - 90 Rotate 90 degrees clockwise.
 - -90 Rotate 90 degrees anticlockwise.
 - 180 Rotate 180 degrees.
 - 270 Rotate 270 degrees.
 - `baseline offset` Indicates how far from the baseline of a paragraph to place an anchored frame. Baseline offset is relevant only for anchored frames whose position attribute is one of inline, sleft, sright, snear, or sfar.
 - `cropped` Indicates whether a wide graphic should be allowed to extend past the margins of the text frame. The `cropped` property is relevant only for anchored frames whose position attribute is one of top, below, or bottom.
 - `dpi` Indicates how to scale an imported graphic object.
 - `entity` Provides the entity name of the imported graphic.
 - `file` Provides the file name of the imported graphic.
 - `floating` Indicates whether the graphic should be allowed to float from the paragraph to which it is attached. The `floating` property is relevant only for anchored frames whose position property is one of top, below, or bottom.
 - `height` Indicates the height of the anchored frame. The height of a single imported graphic object is the sum of the height of the object plus twice the value of the vertical offset property.
 - `horizontal offset` Indicates how far the graphic object is offset from the right and left edges of the anchored frame.
 - `import angle` Indicates an angle of rotation in degrees for the graphic inside its anchored frame.
 - `import by reference or copy` Indicates whether an imported graphic object remains in a separate file or is copied into the FrameMaker document on import from markup.
 - `import size` indicates the size of the imported graphic object by specifying a width and height.

- `near-side offset` Indicates how far to set a frame from the text frame to which the frame is anchored. It is relevant only for anchored frames whose position attribute is one of `sleft`, `sright`, `snear`, or `sfar`.
`val` A number plus a valid unit of measure, e.g. "12pt", "10mm". If not supplied, the value is 0.
 - `position` Indicates where on the page to put the anchored frame. If not supplied, the value is below. Possible anchoring position values are as follows:
 - `inline` At insertion point.
 - `top` At top of column.
 - `below` Below current line.
 - `bottom` At bottom of column.
 - `sleft` Outside column - left side.
 - `sright` Outside column - right side.
 - `snear` Outside column - right side.
 - `sfar` Outside column - side closer to the page edge.
 - `sinside` Outside column - side closer to the binding.
 - `soutside` Outside column - side farther from the binding.
 - `tleft` Outside text frame - left side.
 - `tright` Outside text frame - right side.
 - `tnear` Outside text frame - side closer to the page edge.
 - `tfar` Outside text frame - side farther from the page edge.
 - `tinside` Outside text frame - side closer to the binding.
 - `toutside` Outside text frame - side closer to the binding.
 - `runin` Run into paragraph.
 - `sideways` Indicates that the imported graphic will be flipped left to right to give a mirror image.
 - `vertical offset` Indicates how far the graphic object is offset from the top and bottom edges of the anchored frame.
 - `width` Indicates the width of the anchored frame. The value for a single imported graphic object is the sum of the width of the object plus twice the value of the horizontal offset property.
- For marker elements:
 - `marker text` Provides the text content of the marker.
 - `marker type` Identifies the type of marker.
 - For table elements:

- `column_ruling` Specifies whether all columns should have ruling on their right side. This property does not specify the style or weight of the ruling. The default ruling is defined by the relevant table format in the structured template.
 - `column_widths` The width of successive columns in the table. On import from markup these widths are reapplied regardless of any changes made by the user. If proportional widths are used, the `pgwide` attribute or `page_wide` property determines the table overall width.
 - `columns` The number of columns in the table. This is essential for the correct rendering of the table.
 - `page_wide` This is relevant only to tables whose columns use proportional widths on pages with more than a single column. In this case, the attribute indicates whether the entire table should be the width of the column in which it is anchored, or the width of the overall text frame.
 - `row_ruling` Specifies whether all rows should have ruling on their bottom side. This property does not specify the style or weight of the ruling. The default ruling is defined by the relevant table format in the structured template.

Expected markup attribute value:

 - 0 Rows have no ruling.
 - 1 Rows have ruling.
 - `table_border_ruling` Specifies whether the table should have ruling around its outside borders. This property does not specify the style or weight of the ruling. The default ruling is defined by the relevant table format in the structured template.

Expected markup attribute value:

 - all Rows have no ruling.
 - top Rows have ruling.
 - `table_format` Specifies the table format for all instances of the FrameMaker table element.

Expected markup attribute value: A name of a table format that is present in the application's structured template.
- For table cell elements:
 - `column_name` Associates a name with a cell in a given column.
 - `column_number` Indicates the column number that the cell will start in.
 - `column_ruling` Specifies whether the cell should have ruling on its right side. This property does not specify the style or weight

of the ruling. The default ruling is defined by the relevant table format in the structured template.

Expected markup attribute value:

- 0 Cell has no right side ruling.
- 1 Cell has right side ruling.
- `end column name` Specifies the name of a column that ends a straddle.
- `horizontal straddle` Specifies the number of columns a straddled cell spans.
- `more rows` Specifies the number of additional rows a straddled cell spans.

Expected markup attribute value: An integer greater than 1 and no greater than the number of rows in the table part. The total number of rows the cell occupies is `more rows+1`.

- `rotate` Indicates how much to rotate the contents of a cell.

Expected markup attribute value: The CALS model restricts this property to a boolean value, where 1 indicates a rotation of 90 degrees anti-clockwise. FrameMaker extends the possible values to allow rotations of 0, 90, 180, and 270 degrees.

- `row ruling` Specifies whether the cell should have ruling on its bottom side. This property does not specify the style or weight of the ruling. The default ruling is defined by the relevant table format in the structured template.

Expected markup attribute value:

- 0 Cell has no bottom side ruling.
- 1 Cell has bottom side ruling.
- `span name` Applies a predefined CALS spanspec, starting at this cell.

Expected markup attribute value: A valid spanspec name.

- `start column name` Specifies the name of a column that begins a horizontal straddle.

Expected markup attribute value: A valid column name as defined in a colspec.

- `vertical straddle` Specifies the number of rows a straddled cell spans.

Expected markup attribute value: An integer greater than 1 and no greater than the number of rows in the section (heading, body or footing) of the table that contains the starting cell.

- For table row elements: maximum height, minimum height, row type, or row ruling.
 - maximum height Specifies the maximum height for each row in the table.
Expected markup attribute value: A number plus a valid unit of measure, e.g. "24pt", "15mm". If not supplied, the maximum height of the row is not limited.
 - minimum height Specifies the minimum height for each row in the table.
Expected markup attribute value: A number plus a valid unit of measure, e.g. "12pt", "9mm". If not supplied, the minimum height of the row is not limited.
 - row type Sets the row type as heading, body or footing.
 - row ruling Specifies whether the cell should have ruling on its bottom side. This property does not specify the style or weight of the ruling. The default ruling is defined by the relevant table format in the structured template.
Expected markup attribute value:
 - 0 Cell has no bottom side ruling.
 - 1 Cell has bottom side ruling.
- For CALS table colspecs:
 - cell alignment character
 - cell alignment offset
 - cell alignment type
 - column name
 - column number
 - column ruling
 - column width
 - row ruling
 - vertical alignment
- For CALS table spanspecs:
 - cell alignment character
 - cell alignment offset
 - cell alignment type
 - column ruling
 - end column name
 - row ruling

- span name
- start column name
- vertical alignment

Details

- If you use the `is fm property` rule to translate a markup attribute to a FrameMaker property, the markup attribute does not also appear as a FrameMaker attribute.
- If you use this rule in a highest-level `attribute` rule, it applies only to elements that have that attribute and are of the appropriate type. For example, if you have these declarations:

```
<!ATTLIST (graphic | table) w CDATA #IMPLIED>
```

and these rules:

```
attribute "w" is fm property width;
element "graphic" is fm graphic element;
element "table" is fm table element;
```

the `w` attribute becomes the `width` property of the `graphic` element but remains an attribute for the `table` element, since tables do not have a `width` property. If you intended `w` to be the column width for tables, you should use these rules:

```
element "graphic" {
    is fm graphic element;
    attribute "w" is fm property width;
}

element "table" {
    is fm table element;
    attribute "w" is fm property column width;
}
```

Examples

- The markup attribute `w` may be used for multiple elements to represent the width of a table's columns. To translate it to the FrameMaker property `column width`:

```
attribute "w" is fm property column width;
```

- To translate the attribute `form` to the cross-reference formatting property `cross-reference format` for the element `xref`:

```
element "xref" {
    is fm cross-reference element;
    attribute "form" is fm property cross-reference format;
}
```

See also

Related rules	“fm property” on page 78 “is fm property value,” next
Rules mentioned in synopses	“element” on page 54 “attribute” on page 44
General information on this topic	Developer Guide, page 343: Formatting properties for tables Developer Guide, page 371: Anchored frame properties Developer Guide, page 373: Other graphic properties Developer Guide, Chapter 26, Translating Markers Developer Guide, Chapter 24, Translating Cross-References

is fm property value

Use the `is fm property value` rule when a markup attribute has a name token group as its declared value and you want to rename the individual name tokens when translating to and from FrameMaker property values. Read/write rules do not support double-byte characters, so you cannot use this rule to process attributes with double-byte characters in their names.

Synopsis and contexts

1. `value "token" is fm property value propval;`
2. `attribute "attr" { . . .
 value "token" is fm property value propval;
 . . . }`
3. `element "gi" { . . .
 attribute "attr" { . . .
 value "token" is fm property value propval;
 . . . } . . . }`

Arguments

<i>token</i>	A token in a name token group.
<i>propval</i>	A defined FrameMaker property value.
<i>attr</i>	The name of a markup attribute.
<i>gi</i>	A markup element's name (generic identifier).

Details

- This rule can be used at the highest level to set a default, or within an `attribute` rule.

- Use this rule when the corresponding markup attribute translates to a property in FrameMaker. If the markup attribute translates to a choice attribute instead, you need to use the `is fm value` rule to specify the correspondence between markup tokens and FrameMaker attribute choices.
- When using this rule, remember that markup does not permit a token to appear in the declared value of more than one attribute of an element. For example, the following rule:

```
element "picture" {
  is fm graphic element;
  attribute "place" {
    is fm property position;
    value "left" is fm property value subcol left;
  }
  attribute "just" {
    is fm property alignment;
    value "left" is fm property value align left;
  }
}
<!ATTLIST picture
  place (left, sright, snear, . . .)
  just (left, aright, acenter, . . .)
>
```

- FrameMaker defines the `table border ruling` property for working with tables and the `alignment` and `vertical alignment` properties for working with `colspecs` and `spanspecs`.

If you use the CALS table model for your tables, you should use read/write rules to translate these properties to the `frame`, `align`, and `valign` attributes on appropriate elements. There is also a default correspondence between the FrameMaker property values and the defined value in markup.

If you do not use the CALS table model, you may still choose to translate these FrameMaker formatting properties to markup attributes. In this case, you must also determine the translation from property value to defined value.

- If you use the CALS table model, the `frame` attribute has the following defined values: `all`, `top`, `bottom`, `topbot`, `sides`, and `none`. The values for the corresponding `table border ruling` property are the same as the defined values, except that the `topbot` defined value is the `top` and `bottom` property value.

The `align` attribute and the corresponding `cell alignment type` property have the following values: `left`, `center`, `right`, `justify`, and `char`.

The `valign` attribute and the corresponding `vertical alignment` property have the following values: `top`, `middle`, and `bottom`.

Examples

- To use the `table border ruling` property for a non-CALS table and to set its name tokens, use this rule:

```
element "tab" {
  is fm table element;
  attribute "frame" {
    is fm property table border ruling;
    value "all" is fm property value all;
    value "top" is fm property value top;
    value "bottom" is fm property value bottom;
    value "topbot" is fm property value top and bottom;
    value "sides" is fm property value sides;
    value "none" is fm property value none;
  }
}
```

- To rename the FrameMaker `import by reference or copy` property as the `refcopy` attribute, and to also change the name tokens, use this rule:

```
attribute "refcopy" {
  is fm property import by reference or copy;
  value "r" is fm property value reference;
  value "c" is fm property value copy;
}
```

See also

Related rules	"fm property" on page 78 "is fm property" on page 112
Rules mentioned in synopses	"attribute" on page 44 "element" on page 54 "value" on page 157

is fm reference element

For SGML, use the `is fm reference element` rule to translate an entity in markup to an element defined on a reference page in a FrameMaker document (a reference element). For XML, use this rule to translate an internal entity to a reference element. Read/write rules do not support double-byte characters, so you cannot use this rule to process elements with double-byte characters in their names.

Synopsis and contexts

1. `entity "ename" is fm reference element ["fmtag"];`
2. `reader entity "ename" is fm reference element ["fmtag"];`

Arguments

<i>ename</i>	An entity name.
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

- For SGML, instead of using this rule to translate an `SDATA` entity, you can use a parameter literal of a particular form. For information on how to do so, see [Developer Guide, page 330: Translating SDATA entities as FrameMaker reference elements](#).
- For XML, `SDATA` entities are not allowed—this rule translates internal entities.
- You can use the `is fm reference element` rule within an `entity` rule at the highest level to have the translation occur in both directions. Or you can put the `entity` rule inside a `reader` rule to have the translation occur only when reading an SGML document into FrameMaker. Remember that the `SDATA` entity must be declared in the DTD in order to use this rule.
- The FrameMaker element must occur in a flow named `Reference Elements`. That flow must be on a reference page of the application's template file with a name that starts with `SGML Utilities Page`—for example, `SGML Utilities Page 1` or `SGML Utilities Page Logos`. For information on working with reference pages, see the FrameMaker user guide.
- When FrameMaker encounters references to the specified entity while translating an markup document to FrameMaker, it copies the appropriate element from its reference page in the FrameMaker template associated with the structure application. When it encounters an instance of an element associated with one of the reference pages while writing a FrameMaker document to markup, it generates an entity reference.
- When you use this rule, the *fmtag* element must be defined for your FrameMaker documents and valid in the contexts in which *ename* occurs. If it is not, the resulting FrameMaker document is invalid.

Examples

Assume you have an entity named `legalese` which contains text you need to include in many places. The entity is too long to be a FrameMaker variable, and you don't want to treat it as an entire paragraph. Instead, you can choose to have the entity correspond to a text range element called `LegaleseFragment`.

To do so, add the following rule to your rules document:

```
entity "legalese" is fm reference element "LegaleseFragment";
```

The entity declaration in your DTD looks like this for XML:

```
<!ENTITY legalese ">
```

The entity declaration in your DTD looks like this for SGML:


```
<!ENTITY legalese SDATA "[ ]">
```

Create a reference frame on the reference page of your application which contains the element “LegaleseFragment” with your boilerplate text. In order for the element to be treated as a “text range” use the appropriate TextFormatRules for this element in the EDD.

When FrameMaker translates a markup document that contains the following markup:

```
<para>The rules are &legalese; for this situation.</para>
```

It produces the following element structure:



See also

Rules mentioned in [“entity” on page 59](#)
synopses

General information [Developer Guide, Chapter 21, Translating Entities and Processing](#)
on this topic [Instructions](#)

is fm rubi element

Use the `is fm rubi element` rule to identify a markup element that translates to a Rubi element in FrameMaker. You can choose either to have the same name in both representations or to change the name during translation. Read/write rules do not support double-byte characters, so you cannot use this rule to process elements with double-byte characters in their names.

Synopsis and contexts

```
element "gi" { . . .
    is fm rubi element ["fmtag"];
. . . }
```

Arguments

gi A markup element’s name (generic identifier).

fmtag A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

If you use this rule, the other subrules of the `element` rule that you can use for the same markup element are as follows:

- `attribute` specifies what to do with a markup element's attributes.
- `fm attribute` specifies what to do with attributes present in the FrameMaker representation of the element but not in the markup representation.

Examples

- To translate the markup element `rubitext` to the `Rubitext` element in FrameMaker, use this rule:

```
element "rubitext" is fm rubi element;
```

- To translate it to the `MyRubiTextp` element, use this rule:

```
element "rubitext" is fm rubi element "MyRubiText";
```

See also

Rules mentioned in ["element" on page 54](#)
synopses

General information [Developer Guide, Chapter 20, Translating Elements and Their Attributes](#)
on this topic

is fm rubi group element

Use the `is fm rubi group element` rule to identify a markup element that translates to a Rubi group element in FrameMaker. You can choose either to have the same name in both representations or to change the name during translation. Read/write rules do not support double-byte characters, so you cannot use this rule to process elements with double-byte characters in their names.

Synopsis and contexts

```
element "gi" { . . .  
    is fm rubi group element ["fmtag"];  
    . . . }
```

Arguments

gi A markup element's name (generic identifier).

fmtag A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

If you use this rule, the other subrules of the `element` rule that you can use for the same markup element are as follows:

- `attribute` specifies what to do with a markup element's attributes.
- `fm attribute` specifies what to do with attributes present in the FrameMaker representation of the element but not in the markup representation.

Examples

- To translate the markup element `rubigroup` to the `Rubigroup` element in FrameMaker, use this rule:

```
element "rubigroup" is fm rubi group element;
```

- To translate it to the `MyRubiGroup` element, use this rule:

```
element "rubigroup" is fm rubi group element "MyRubiGroup";
```

See also

Rules mentioned in ["element" on page 54](#)
synopses

General information [Developer Guide, Chapter 20, Translating Elements and Their Attributes](#)
on this topic

is fm system variable element

Use the `is fm system variable element` rule to identify a markup element that translates to a system variable element in FrameMaker. You can choose either to have the same name in both representations or to change the name during translation. Read/write rules do not support double-byte characters, so you cannot use this rule to process elements with double-byte characters in their names.

Synopsis and contexts

```
element "gi" { . . .  
    is fm system variable element ["fmtag"];  
    . . . }
```

Arguments

gi A markup element's name (generic identifier).

fmtag A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

- If you use this rule, the other subrules of the `element` rule that you can use for the same markup element are:
 - `attribute` specifies what to do with a markup element's attributes.
 - `fm attribute` specifies what to do with attributes present in the FrameMaker representation of the element but not in the markup representation.
- This rule does not apply to translating non-element FrameMaker variables.

Examples

To translate the markup element `date` to the `Date` system variable element in FrameMaker, use this rule:

```
element "date" is fm system variable element;
```

You specify which system variable to use by adding a rule to the `Date` element's definition in the FrameMaker EDD. For example:

Element (System Variable):Date

System variable format rule

In all contexts.

Use system variable:Current Date (Long)

See also

Related rules ["is fm variable" on page 133](#)

["fm variable" on page 87](#)

Rules mentioned in ["element" on page 54](#)
synopses

General information [Developer Guide, Chapter 25, Translating Variables and System Variable
on this topic Elements](#)

is fm table element

Use the `is fm table element` rule to identify a markup element that translates to a table element in FrameMaker. You can choose either to have the same name in both representations or

to change the name during translation. Read/write rules do not support double-byte characters, so you cannot use this rule to process elements with double-byte characters in their names.

Synopsis and contexts

```
element "gi" { . . .  
    is fm table element ["fmtag"];  
    . . . }
```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

- If you use the CALS table model, you do not need to use this rule to translate the CALS `table` element properly.
- If your markup element declarations for a table element do not include an attribute that corresponds to the `columns` property, you must use the `fm property` rule to specify a number of columns for the table.
- If you use this rule, the other subrules of the `element` rule that you can use for the same markup element are as follows:
 - `attribute` specifies what to do with a markup element's attributes.
 - `fm attribute` specifies what to do with attributes present in the FrameMaker representation of the element but not in the markup representation.
 - `fm property` specifies what to do with FrameMaker properties associated with the element.
 - reader [insert table part element](#) indicates that the software should insert the indicated table part (table title, table heading, or table footing), even if the markup element structure or instance does not contain the corresponding element.

Examples

- To translate the markup element `gloss` to the `Gloss` table element in FrameMaker, use this rule:

```
element "gloss" is fm table element;
```

- To translate it to the `Glossary` table element, use this rule:

```
element "gloss" is fm table element "Glossary";
```

See also

Rules mentioned in ["element" on page 54](#)
synopses

General information [Developer Guide, Chapter 22, Translating Tables](#)
on this topic

is fm table part element

Use the `is fm table part` element rule to identify a markup element that translates to a table part element in FrameMaker, such as a table title element. You can choose either to have the same name in both representations or to change the name during translation. Read/write rules do not support double-byte characters, so you cannot use this rule to process elements with double-byte characters in their names.

Synopsis and contexts

```
element "gi" { . . .  
    is fm table part element ["fmtag"];  
    . . . }
```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>part</i>	A FrameMaker table part. One of the keywords: <code>title</code> , <code>body</code> , <code>heading</code> , <code>footing</code> , <code>row</code> , <code>cell</code> .
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

- If you use the CALS table model, you do not need to use this rule to translate elements representing parts of tables in CALS properly.
- If you map a markup element to a FrameMaker table part element, then the element cannot be used anywhere in the instance except as that table part. For example, if you have a "title" element and you use the following rule:

```
element "title" is fm table title element;
```

Then you would not be able to insert a "title" element in a `Chapter` element.

- If you use this rule, the other subrules of the `element` rule that you can use for the same markup element are as follows:
 - `attribute` specifies what to do with a markup element's attributes.
 - `fm attribute` specifies what to do with attributes present in the FrameMaker representation of the element but not in the markup representation.
 - `fm property` specifies what to do with FrameMaker properties associated with the element.

- reader [end vertical straddle](#) indicates that the associated table row or cell element terminates a vertical table straddle. This subrule applies only if *part* is row or cell.
- reader [start new row](#) indicates that the associated table cell element indicates the start of a new row in the table. This subrule applies only if *part* is cell.
- reader [start vertical straddle](#) indicates that the associated table cell element starts a vertical table straddle. This subrule applies only if *part* is cell.

Examples

- To translate the markup element `head` as the FrameMaker table heading element `Head`, use this rule:

```
element "head" is fm table heading element;
```

- To translate the markup element `dfn` as the FrameMaker table cell element `Definition`, use this rule:

```
element "dfn" is fm table cell element;
```

See also

Rules mentioned in [“element” on page 54](#)
synopses

General information [Developer Guide, Chapter 22, Translating Tables](#)
on this topic

is fm text inset

Use the `is fm text inset` rule to translate a declared entity to a text inset in FrameMaker. While you can translate any entity to a text inset, we suggest you only do this with `SDATA` entities when working with SGML. Read/write rules do not support double-byte characters, so you cannot use this rule to process elements with double-byte characters in their names.

Note: XML: The XML standard does not allow `SDATA` entities, so you cannot use this rule for that purpose. FrameMaker translates external text entities as text insets by default, so this rule is not necessary for that type of entity.

Synopsis and contexts

1. entity "ename" is fm text inset "fname"
 [in *body_or_ref* flow "*flowname*"];
2. reader entity "ename" is fm text inset "fname"
 [in *body_or_ref* flow "*flowname*"];

Arguments

<i>ename</i>	An entity name.
<i>fname</i>	A filename containing the text to include. This file must be a FrameMaker document or a file of a type for which FrameMaker has a filter, for example, a MS-Word document.
<i>body_or_ref</i>	One of the keywords: <i>body</i> or <i>reference</i> , indicating the type of text flow in which to find the text to include. You can specify this option only if <i>fname</i> is a FrameMaker document.
<i>flowname</i>	The name of the FrameMaker text flow.

Details

- By default, external text entities in markup are imported as text insets. For the markup to be valid, the external text entities must be text, XML, or SGML files. In the FrameMaker document, the text insets use these files as their sources. It is probably most advantageous to retain these files for the text insets; you do not need to use the `is fm text inset` rule to import external text entities as text insets.
- The source file for the text inset must either be a FrameMaker file or a file of a format FrameMaker can filter automatically. You cannot use an SGML file as the source of the text inset.
- Instead of using this rule to translate an SGML `SDATA` entity to a text inset, you can use a parameter literal of a particular form. For information on how to do so, see [Developer Guide, page 328: Translating SDATA entities as FrameMaker text insets](#).
- You can use the `is fm text inset` rule within an `entity` rule at the highest level to have the translation occur in both directions. Or you can put the `entity` rule inside a `reader` rule to have the translation occur only when reading an SGML document into FrameMaker.
- If *fname* is not a FrameMaker document, you cannot specify the `in body flow` or `in reference flow` options. In this case, FrameMaker uses all of the text in the file specified by *fname* for the text inset.

If *fname* is a FrameMaker document and you do not specify a flow to use, FrameMaker use the contents of the main body flow of the specified document.

- **Important:** *flowname* must exactly match the name of a flow in the document. If there is no match for the type of flow you specify (body or reference), then a crash will result. If there is more than one matching flow, FrameMaker uses the first matching flow.
- By default, the software reformats the text inset to conform to the format rules of the document containing the text inset. If the source for the text inset has element structure, FrameMaker also retains that element structure.

You can confirm this behavior with the `reformat using target document catalogs` rule. You can change this behavior using the subrules `reformat as plain text` or `retain source document formatting`.

- FrameMaker requires that a structured flow have exactly one highest-level element. For this reason, you cannot use a single text inset to include multiple elements at the top level of the inset. You must use multiple text insets for this purpose.
- FrameMaker puts an end-of-paragraph symbol after a text inset. For this reason, you cannot use a text inset to insert a range of text inside a single paragraph. To do so, you can translate the entity either as a FrameMaker variable (with the `is fm variable` rule) or as a reference element (with the `is fm reference element` rule).

Examples

Assume you have declared an SGML SDATA entity. You also have a single paragraph of boilerplate text to be used in your documents. You can place this text on a reference page in a text column with a flow called `BoilerPlate` in the FrameMaker template for your SGML application. If that template is the file `template.doc`, you could use this rule to translate occurrences of the `boiler` entity to a text inset in corresponding FrameMaker documents:

```
entity "boiler"  
  is fm text inset "template.doc"  
  in reference flow "BoilerPlate";
```

See also

Related rules	“reformat as plain text” on page 146 “reformat using target document catalogs” on page 147 “retain source document formatting” on page 148 “is fm reference element” on page 121 “is fm variable” on page 133
Rules mentioned in synopses	“entity” on page 59 “reader” on page 145
General information on this topic	Developer Guide, Chapter 21, Translating Entities and Processing Instructions

is fm value

Use the `is fm value` rule to translate the value of a markup attribute to a particular choice for a FrameMaker choice attribute. The attribute’s declared value must be a name token group or NOTATION.

Synopsis and contexts

```
1. value "token" is fm value "val";
```

```
2. attribute "attr" { . . .
    value "token" is fm value "val";
    . . . }

3. element "gi" { . . .
    attribute "attr" { . . .
        value "token" is fm value "val";
    . . . } . . . }
```

Arguments

token A token in a name token group.

val An allowed value for a FrameMaker choice attribute.

attr The name of a markup attribute.

gi A markup element's name (generic identifier).

Details

Use this rule when the corresponding markup attribute translates to a choice attribute in FrameMaker. If the markup attribute translates to a FrameMaker property, you need to use the `is fm property value` rule to specify the correspondence between markup tokens and FrameMaker property values.

Examples

- If the token list (`r | b | g`) is used by multiple attributes, you can use these rules to translate the individual tokens consistently:

```
value "r" is fm value "Red";
value "b" is fm value "Blue";
value "g" is fm value "Green";
```
- If the token list (`r | b | g`) is used by several attributes as above but by the `bird` element differently, you can add this rule to the above rules:

```
element "bird" {is fm element;
    ] attribute "species" {
        value "r" is fm value "Robin";
        value "b" is fm value "Blue Jay";
        value "g" is fm value "Goldfinch";
    }}]
```

See also

Related rules ["is fm property value" on page 119](#)

Rules mentioned in synopses	"attribute" on page 44 "element" on page 54 "value" on page 157
General information on this topic	Developer Guide, Chapter 20, Translating Elements and Their Attributes

is fm variable

Use the `is fm variable` rule to translate a declared markup text entity to a FrameMaker non-element variable.

Synopsis and contexts

1. `entity "ename" is fm variable ["var"];`
2. `reader entity "ename" is fm variable ["var"];`

Arguments

<i>ename</i>	An entity name.
<i>var</i>	A FrameMaker variable name.

Details

You can use the `is fm variable` rule within an `entity` rule at the highest level to have the translation occur in both directions. Or you can put the `entity` rule inside a `reader` rule to have the translation occur only when reading a markup document into FrameMaker.

Examples

- To translate the markup element `v` to a non-element FrameMaker variable of the same name:

```
entity "v" is fm variable;
```
- To translate the FrameMaker variable `Licensor` to the markup element `lic`, use this rule:

```
entity "lic" is fm variable "Licensor";
```

See also

Related rules	"fm variable" on page 87 "is fm system variable element" on page 125
Rules mentioned in synopses	"entity" on page 59
General information on this topic	Developer Guide, Chapter 25, Translating Variables and System Variable Elements

is processing instruction

On export, you use the `is processing instruction` rule to tell FrameMaker to create processing instructions for all non-element markers or for non-element markers of a particular type. By default, FrameMaker creates processing instructions for all non-element markers. You have the option of discarding non-element markers; you might use this rule in conjunction with the `drop` rule when you want to discard some but not all non-element markers.

Synopsis and contexts

```
fm marker ["type1", . . . , "typen"] is processing instruction;
```

Arguments

type_i A FrameMaker marker type, such as Index or Type 22.

Details

If you do not supply any *type_i* arguments, this rule applies to all non-element markers other than markers of the type reserved by FrameMaker for storing processing instructions, PI entities, and external data entities. (By default, the reserved marker types are DOC PI, DOC Entity Reference, and DOC Comment.)

Examples

To discard all nonelement markers other than Index markers, use these rules:

```
fm marker "Index" is processing instruction;
fm marker drop;
```

See also

Rules mentioned in [“fm marker” on page 76](#)
synopses

General information [Developer Guide, Chapter 26, Translating Markers](#)
on this topic

line break

Use the `line break` rule to tell FrameMaker about any limits on the length of lines in a markup file it generates. You also use it to tell the software whether or not to interpret line breaks in a markup document as FrameMaker paragraph breaks within elements.

Synopsis and contexts

1. reader **line break** is *mode*;
2. writer **line break** is *mode*;

```
3. element "gi" { . . .
    reader { . . .
        line break is mode;
    . . . } . . . }
4. element "gi" { . . .
    writer { . . .
        line break is mode;
    . . . } . . . }
```

Arguments

mode For writer: *n* characters (where *n* is a positive integer in C syntax).
For reader: one of `forced` `return` or `space`.

gi A markup element's name (generic identifier).

Details

- This rule can be used at the highest level to set a default or within an `element` rule to set line breaks for only that element.
- On export, FrameMaker behaves as follows:
When exporting the text of a paragraph, it ignores line breaks. It includes a space separating the two words on either side of a line break and attempts to avoid generating lines longer than *n* characters (the default is 80). It maintains a counter indicating how many characters it has placed on a single line. After this counter reaches *n*-10, it changes the next data character space to a record end.
It generates a markup record end at the end of every paragraph and flow in the FrameMaker document.
If you want a start-tag for an element and its contents to appear on the same line in the markup document, you must write aa structure API client.
- On import you have control over record ends not ignored by the underlying parser. Within a `reader` rule, *mode* can be one of the following:
`forced` `return` informs FrameMaker that a line break within a text segment should be converted to a forced return.
`space` informs FrameMaker that a line break within a text segment should be treated as a space. This is the default.

Examples

Line breaks may need to be treated differently within different elements. For example, a line break within an `example` element may need to be preserved on import, while a line break within a `par` element may be a word break:

```
element "example" reader line break is forced return;
element "par" reader line break is space;
```

marker text is

Use the `marker text is` rule to indicate whether the text of a marker element should become an attribute value or the content of the corresponding markup element. Note that the markup element must not be declared as empty if you want the marker text to be translated as content.

Synopsis and contexts

```
element "gi" { . . .
    is fm marker element ["fmtag"];
    marker text is attr_or_content;
    . . . }
```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.
<i>attr_or_content</i>	One of the keywords: <code>attribute</code> or <code>content</code> .

Details

- By default, FrameMaker translates a marker element in FrameMaker to a markup empty element. It writes the marker text as the value of the markup element's `text` attribute.
- Instead of the default, you can have FrameMaker translate a marker element to a markup element whose content model is `#PCDATA`. The marker text becomes the element's content.

Examples

- To state that the markup element `mkr` corresponds to the FrameMaker element `Marker` and to confirm the default behavior, you can use this rule:

```
element "mkr" {
    is fm marker element "Marker";
    marker text is attribute;
}
```

With this rule, the FrameMaker element definition:

Element (Marker): Marker

corresponds to the DTD declarations:

```
<!ELEMENT mkr EMPTY>
<!ATTLIST mkr
    text CDATA #IMPLIED
    type CDATA #IMPLIED>
```

In this case, if the FrameMaker document contains an instance of the `Marker` element whose marker text is "Some marker text" and whose type is Type 22, the markup output includes:

```
<mkr text="Some marker text" type="Type 22"/>
```

- To state that the markup element `mkr` corresponds to the FrameMaker element `Marker` but that the marker text should become element content in markup, you can use this rule:

```
element "mkr" {
    is fm marker element "Marker";
    marker text is content;
}
```

With this rule, the FrameMaker element definition:

Element (Marker): Marker

corresponds to the DTD declarations:

```
<!ELEMENT mkr (#PCDATA)>
<!ATTLIST mkr type CDATA #IMPLIED>
```

In this case, if the FrameMaker document contains an instance of the `Marker` element whose marker text is "Some marker text" and whose type is Type 22, the output includes:

```
<mkr type="Type 22">
Some marker text
</mkr>
```

See also

Rules mentioned in synopses	"element" on page 54 "is fm marker element" on page 111
General information on this topic	Developer Guide, Chapter 26, Translating Markers

notation is

Use the `notation is` rule only in an `element` rule for a graphic or equation element, to provide information the software needs when writing a document containing graphics and equations to markup. FrameMaker uses this rule to determine the data content notation name to include in entity declarations it generates.

Synopsis and contexts

```
1. element "gi" {
    is fm equation element ["fmtag"];
    writer equation notation is "notation";
    . . .}}
```

```

2. element "gi" {
    is fm graphic element ["fmtag"];
    writer anchored frame notation is "notation";
    . . .}}

3. element "gi" {
    is fm graphic element ["fmtag"];
    writer facet "facetname" notation is "notation";
    . . .}}

```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.
<i>type</i>	<p>One of the rules <code>anchored frame</code>, <code>facet</code>, or <code>equation</code>. If <code>facet</code>, you must also supply the <code>facetname</code> argument.</p> <p>If <i>type</i> is <code>equation</code>, the rule applies to equation elements.</p> <p>If <i>type</i> is <code>facet</code>, the rule applies to a graphic element that contains only a single facet with the name specified by <code>facetname</code>. This occurs when the graphic element is an anchored frame containing only a single imported graphic object whose original file was in the <code>facetname</code> graphic format. You can use this rule with <i>type</i> set to <code>facet</code> multiple times if you want the software to treat several file formats differently.</p> <p>If <i>type</i> is <code>anchored frame</code>, the rule applies to a graphic element under all other circumstances.</p>
<i>facetname</i>	A facet name. The string for the <code>facetname</code> must exactly match the string for the <code>facetname</code> in the FrameMaker document. To determine a graphic file's <code>facetname</code> , select the graphic, click <code>Graphics>ObjectProperties</code> , and observe the <code>facetname</code> in the dialog box.
<i>notation</i>	A string representing a data content notation name.

Details

By default, FrameMaker uses the first eight characters of the name of the facet it exports as the data content notation. If the graphic or equation has only internal FrameMaker facets, the software uses CGM as the data content notation.

Examples

Assume your end users use the `af` graphic element within FrameMaker, creating the graphics using FrameMaker tools, but want to store them in TIFF format on export. Furthermore, you want

to name the files based on the FrameMaker document's name, but with an extension of `.gr`. You can accomplish this with the following rule:

```
element "af" {
  is fm graphic element;
  writer anchored frame {
    notation is "TIFF";
    export to file "${docname}.gr";
  }
}
```

If you export the FrameMaker file `intro.doc`, the software writes the following entity declaration for the first instance of the `af` element that it finds:

```
<!ENTITY af1 SYSTEM "intro1.gr" NDATA TIFF>
```

See also

Related rules ["convert referenced graphics" on page 49](#)
["entity name is" on page 61](#)
["export to file" on page 67](#)
["specify size in" on page 149](#)

Rules mentioned in
synopses ["element" on page 54](#)
["is fm graphic element" on page 109](#)
["is fm equation element" on page 107](#)
["anchored frame" on page 41](#)
["equation" on page 63](#)
["facet" on page 72](#)
["writer" on page 160](#)

General information [Developer Guide, Chapter 23, Translating Graphics and Equations on this topic](#)

output book processing instructions

By default, when FrameMaker converts a FrameMaker book to markup, it puts `?FM book?` and `?FM document?` processing instructions in the markup document to indicate where the individual files in the FrameMaker documents began. You use the `output book processing instructions` rule to confirm or change this behavior.

Synopsis and contexts

```
writer [do not] output book processing instructions;
```

ArgumentsNone.

Details

If you use the `generate book` rule to tell FrameMaker to use elements to identify book components when reading a markup document, you might choose to not have it output processing instructions when writing the book to markup. In this case, use this rule:

```
writer do not output book processing instructions;
```

See also

Related rules [“generate book” on page 89](#)

General information [Chapter 28, “Processing Multiple Files as Books”](#)
on this topic

preserve fm element definition

Use the `preserve fm element definition` rule to tell FrameMaker, when it is updating an EDD from a revised DTD, not to update the definition of a set of FrameMaker elements and their attributes on the basis of the DTD and other rules.

Synopsis and contexts

```
reader { . . .  
    preserve fm element definition "fmtag1"[, . . ., "fmtagN"];  
    . . . }
```

Arguments

fmtag_i A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

FrameMaker uses the `preserve fm element definition` rule only when updating an EDD from a DTD. By default, when it updates an existing EDD, the software changes the definitions of FrameMaker elements to reflect the new DTD and all read/write rules. You may not want the definition of the FrameMaker element to change. For example, if one of your rules is to unwrap the element `body`, then any element with a definition that includes `body` will be modified directly include the contents of `body` instead of including `body`.

Examples

- Assume you have the rule:

```
fm element "Body" unwrap;
```

and the element definitions:

Element (Container): Figure1

General rule: Caption, Body

Element (Container): Figure2

General rule: Body, Footer

Element (Container): Body

General rule: Header, Line+

The corresponding declarations are:

```
<!ELEMENT figure1 (caption, header, line+)>
<!ELEMENT figure2 (header, line+, footer)>
```

If you update the EDD containing the preceding definitions and use as input the DTD with the preceding declarations, FrameMaker replaces the definitions of `Figure1` and `Figure2` with:

Element (Container): Figure1

General rule: Caption, Header, Line+

Element (Container): Figure2

General rule: Header, Line+, Footer

If you wish to retain the original definitions of `Figure1` and `Figure2` in the revised EDD, include this rule:

```
reader preserve fm element definition "Figure1", "Figure2";
```

- Suppose you want to use a structure API client to reverse the order of child elements in corresponding markup and FrameMaker elements. For example, assume you have the declaration:

```
<!ELEMENT ex (a, b)>
```

and the FrameMaker element definition:

Element (Container): Ex

General rule: B, A

If you have no rules and update the EDD in this situation, FrameMaker updates the definition of `Ex` to correspond to the markup declaration. To suppress this change, use this rule:

```
reader preserve fm element definition "Ex";
```

See also

Related rules [“drop” on page 51](#)
 [“unwrap” on page 154](#)

preserve line breaks

Use the `preserve line breaks` rule to tell FrameMaker to keep line breaks for an element when importing and exporting markup documents. When importing markup, it translates every RE in the element as a forced return. When exporting markup, it translates forced returns as RE characters, and the line ends FrameMaker creates when automatically wrapping the text as non-

RE line breaks in the markup file. This is useful for elements that use RE characters to insert white space in an element's content.

Synopsis and contexts

```
element { . . .  
    preserve line breaks ;  
    . . . }
```

ArgumentsNone

Details

- For an element using this rule, the software writes a an RE (line break) immediately after the open tag and immediately before the close tag.
- For an element using this rule, on export, FrameMaker writes a space character entity reference and an RE (line break) for each necessary line break in the markup file. See the “line break” rule for information on how FrameMaker determines where to put these line breaks by default. Forced returns (shift-return) translate as RE characters (line breaks) in the markup file.
- For SGML, the space character entity uses the ISO entities reference (`&#SPACE`).
- For XML, no entity reference is written for the space character.
- For XML, this rule adds the `xml:space` attribute to the affected elements, with a value of `preserved`. This attribute directs XML applications to respect the whitespace characters in the element's content. On import this attribute is retained—if the EDD for your template does not specify an `xml:space` attribute for the given element, then that attribute will be invalid. You can either define this attribute in your EDD, or use read/write rules to drop the attribute on import.
- For export and import to have the same results, `preserve line breaks` must be specified for the same elements. For example, assume you use `preserve line breaks` on export for an element named `Code`. FrameMaker writes a space character entity reference and an RE (line break) when a line approaches the maximum line length, and it writes RE characters (line breaks) for forced returns. Now assume you remove `preserve line breaks` from the rules for the `Code` element. On import, FrameMaker will translate as spaces the space character entity reference/RE pairs, and as spaces any RE characters (line breaks) not removed by the parser (default behavior). Thus the forced returns (shift-return) are lost and the imported file is not the same as the exported file.
- When importing markup, `preserve line breaks` overrides the `line break is space` rule, if that rule is set. On import, `preserve line breaks` has the same effect for the specified element as the `line break is forced return` rule.

Examples

The following rule preserves line breaks on import and export for the element named code:

```
fm element "code" {
    is fm element "Code";
    preserve line breaks;
}
```

See also

Rules mentioned in [“element” on page 54](#)
synopses

Related rules [“line break” on page 134](#)

processing instruction

Use the `processing instruction` rule to drop processing instructions that are not recognized by FrameMaker. By default, the software stores such processing instructions as the marker text in non-element markers of type DOC PI and DOC Comment.

Synopsis and contexts

```
processing instruction drop;
```

ArgumentsNone

Details

- When you translate a markup document to FrameMaker and the software encounters an unrecognized processing instruction such as:

```
<?mypi?>
```

it stores the processing instruction as the text of a non-element DOC PI marker by default, with the following as the marker text:

```
mypi
```

When you translate a FrameMaker document to markup, it outputs the corresponding processing instruction if it finds a non-element DOC PI marker with text in that format.

- This rule does not affect how FrameMaker treats the processing instructions it does recognize for books, book components, and other non-element markers.

Examples

To discard all unrecognized processing instructions, use this rule:

```
processing instruction drop;
```

See also

Rules mentioned in synopses [“drop” on page 51](#)

General information on this topic [Developer Guide, Chapter 21, Translating Entities and Processing Instructions](#)

proportional width resolution is

Use the `proportional width resolution is` rule to change the number used as the total for proportional column widths in tables. By default, if FrameMaker writes proportional columns widths, those widths add to 100.

Synopsis and contexts

```
writer proportional width resolution is "value";
```

Arguments

value An integer indicating the total for proportional column width values.

Details

Using this rule does not indicate that FrameMaker uses proportional widths, only that if FrameMaker writes proportional widths, then those widths add to *value* instead of 100. To tell FrameMaker to use proportional widths, you must include the `use proportional widths` rule.

Examples

- Assume you do not use the `proportional width resolution is` rule, but have this rule:

```
writer use proportional widths;
```

Further assume you have a 5-column table whose first two columns are 1 inch wide and whose last three columns are 2 inches wide. If the column widths are written to the `colwidth` attribute of the markup `table` element, then FrameMaker creates this start-tag for that table:

```
<table colwidth="12.5* 12.5* 25* 25* 25*">
```

- Assume you have the same table as in the last example and you use this rule:

```
writer {  
  use proportional widths;  
  proportional width resolution is "8";  
}
```

FrameMaker writes this start-tag for the table:

```
<table colwidth="1* 1* 2* 2* 2*">
```

- Assume you have the same table as in the previous examples and you use this rule:

```
writer proportional width resolution is "8";
```

That is, you do not also have the `use proportional widths` rule. In this case, FrameMaker ignores the “proportional width resolution” rule and writes this start-tag for the table:

```
<table colwidth="1in 1in 2in 2in 2in">
```

See also

Related rules [“use proportional widths” on page 156](#)

General information [Developer Guide, Chapter 22, Translating Tables on this topic](#)

put element

See [“generate book” on page 89](#).

reader

The `reader` rule indicates a rule that applies only on import to FrameMaker. It can be used at the highest level to set a default, or within an `element` rule to specify information particular to that element.

Synopsis and contexts

1. `element "gi" { . . .
 reader { . . .
 subrule;
 . . . } . . . }`
2. `reader { . . .
 subrule;
 . . . }`

Arguments

gi A markup element’s name (generic identifier).

subrule Valid subrules:

`character map` changes how FrameMaker translates between individual characters in the markup and FrameMaker character sets. Allowed only at the highest level.

`drop content` imports only the element itself, not its contents. Allowed only within an `element` rule.

`end vertical straddle` specifies the end of a vertical straddle in a table. Allowed only within an `element` rule for a table cell or row element.

`entity` specifies the treatment of an entity in FrameMaker. Allowed only at the highest level.

`generate book` specifies how to identify book components in a markup document. Allowed only at the highest level.

`insert table part element` specifies that FrameMaker should generate a table part (table title, table heading, or table footing) even if there is no content for that part. Allowed only within an `element` rule for a table element.

`line break` changes the treatment of line breaks in the markup instance which are not handled by the parser on import. Allowed at the highest level or within an `element` rule.

`preserve fm element definition` instructs the software not to modify a FrameMaker element definition when updating an existing EDD. Allowed only at the highest level.

`start new row` specifies that this table cell element starts a new row in the table. Allowed only within an `element` rule for a table row element.

`start vertical straddle` specifies the start of a vertical straddle in a table. Allowed only within an `element` rule for a table cell element.

`table ruling style is` specifies the ruling style to apply to all tables. Allowed only at the highest level.

Examples

To change the default ruling style for tables:

```
reader table ruling style is "thick";
```

reformat as plain text

Use the `reformat as plain text` rule in an `entity` rule for an entity you want to translate as a text inset in FrameMaker. This specifies that the software should remove any element structure from the text inset and reformat the text using the format rules of the document into which the text inset is placed. You specify the other choices for formatting text insets with the

rules `reformat using target document catalogs` and `retain source document formatting`.

Synopsis and contexts

1. entity "ename" {
 is fm text inset "fname";
 reformat as plain text;
 . . .}
2. reader entity "ename" {
 is fm text inset "fname";
 reformat as plain text;
 . . .}

Arguments

ename An entity name.

See also

Related rules	"reformat using target document catalogs," next "retain source document formatting" on page 148
Rules mentioned in synopses	"entity" on page 59 "is fm text inset" on page 129
General information on this topic	Developer Guide, Chapter 21, Translating Entities and Processing Instructions

reformat using target document catalogs

Use the `reformat using target document catalogs` rule in an entity rule for an entity you want to translate as a text inset in FrameMaker. This specifies that the software should retain any element structure from the text inset and reformat the text using the format rules of the document into which the text inset is placed. This is the default behavior for entities treated as text insets. You specify the other choices for formatting text insets with the rules `reformat as plain text` and `retain source document formatting`.

Synopsis and contexts

1. entity "ename" {
 is fm text inset "fname";
 reformat using target document catalogs;
 . . .}

```
2. reader entity "ename" {
    is fm text inset "fname";
    reformat using target document catalogs;
    . . .}
```

Arguments

ename An entity name.

See also

Related rules [“reformat as plain text,”](#) (the previous section)
 [“retain source document formatting”](#) on page 148

Rules mentioned in [“entity”](#) on page 59
synopses [“is fm text inset”](#) on page 129

General information [Developer Guide, Chapter 21, Translating Entities and Processing](#)
on this topic [Instructions](#)

retain source document formatting

Use the `retain source document formatting` rule in an entity rule for an entity you want to translate as a text inset in FrameMaker. This specifies that the software should remove any element structure from the text inset, but keep the formatting of the source document, rather than reformatting it according to the rules of the document that contains the text inset. You specify the other choices for formatting text insets with the rules `reformat as plain text` and `reformat using target document catalogs`.

Synopsis and contexts

```
1. entity "ename" {
    is fm text inset "fname";
    retain source document formatting;
    . . .}

2. reader entity "ename" {
    is fm text inset "fname";
    retain source document formatting;
    . . .}
```

Arguments

ename An entity name.

See also

Related rules	“reformat as plain text” on page 146 “reformat using target document catalogs,” (the previous section)
Rules mentioned in synopses	“entity” on page 59 “is fm text inset” on page 129
General information on this topic	Developer Guide, Chapter 21, Translating Entities and Processing Instructions

specify size in

Use the `specify size in` rule only in an `element` rule for a graphic or equation element, to provide information the software needs when writing a document containing graphics and equations to markup. This rule determines which of the `dpi` or the `impsize` attribute FrameMaker uses to indicate the size of a graphic or equation. The rule also indicates what units are used for `impsize` and the resolution in which sizes are reported is always 0.001. If there is no `specify size in` rule, FrameMaker uses the `dpi` attribute.

Synopsis and contexts

1. `element "gi" {
 is fm equation element ["fmtag"];
 writer equation specify size in units
 . . .}`
2. `element "gi" {
 is fm graphic element ["fmtag"];
 writer anchored frame specify size in units
 . . .}`
3. `element "gi" {
 is fm graphic element ["fmtag"];
 writer facet "facetname" specify size in units
 . . .}`

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.
<i>facetname</i>	A facet name. The string for the facetname must exactly match the string for the facetname in the FrameMaker document. To determine a graphic

file's facetname, select the graphic, click Graphics>ObjectProperties, and observe the facetname in the dialog box.

units The units in which the size of the element is coded. Valid values: cm, cc, dd, in, mm, pc, pi, or pt.

Details

- Use this rule when you export FrameMaker documents to markup documents.
- FrameMaker reports the size of the elements in the indicated units, at a fixed resolution of 0.001.

Examples

- Suppose your document has a graphic element, `graph`, containing an Anchored Frame sized to fit a FrameMaker-drawn circle with a diameter of 3.15 centimeters. Given the rule:

```
element "graph" {
    is fm graphic element;
    writer anchored frame specify size in cm;
}
```

FrameMaker generates the attribute `height="3.150cm"` and attribute `width="3.150cm"`.

- With the same graphic, if the rule is:

```
element "graph" {
    is fm graphic element;
    writer anchored frame specify size in mm;
}
```

FrameMaker generates `height="31.500mm"` and attribute `width="31.500mm"`.

See also

Related rules ["convert referenced graphics" on page 49](#)
 ["entity name is" on page 61](#)
 ["export to file" on page 67](#)
 ["specify size in" on page 149](#)

Rules mentioned in synopses	“element” on page 54 “is fm graphic element” on page 109 “is fm equation element” on page 107 “anchored frame” on page 41 “equation” on page 63 “facet” on page 72 “writer” on page 160
General information on this topic	Developer Guide, Chapter 23, Translating Graphics and Equations

start new row

Use the `start new row` rule in the `element` rule for a table cell element to specify that an occurrence of the table cell element indicates that FrameMaker should start a new table row to contain that cell.

Synopsis and contexts

```

element "gi" { . . .
    is fm table cell element ["fmtag"];
    reader start new row ["name"];
. . . }
```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.
<i>name</i>	An optional name to identify this row

Details

- Your DTD may contain elements that you want to format as tables in FrameMaker even though the element hierarchy does not match that required by FrameMaker for tables. In such a situation, the nature of the element hierarchy may indicate where new rows should begin.
- In some cases, you can use a rule such as the following to indicate that a table cell starts a new row:

```

element "gi" {
    is fm table cell element;
    fm property column number value is "1";
}
```

With this rule, when FrameMaker encounters a *gi* element, it tries to place that element in the first column of the current table row. If there is already a cell in the first column of the current row, the software automatically creates a new row for *gi*. In this situation, you would not also need the `start new row` rule.

However, if there is not already a cell in the first column of the current row when the software encounters a *gi* element, it puts the *gi* cell in the current row and does not create a new row for it. This can happen if the table has a vertical straddle in the first column. When FrameMaker encounters a *gi* element on a row that should have a vertical straddle in the first column, with only the rule above, the software puts the *gi* element in the same row (because that cell isn't occupied). To guarantee a new row starts with the occurrence of *gi* instead, you should use this rule:

```
element "gi" {
    is fm table cell element;
    fm property column number value is "1";
    reader start new row;
}
```

Examples

For a complete example using the `start new row` rule, see [Developer Guide, page 352: Omitting explicit representation of table parts](#).

See also

Related rules	"start vertical straddle," next
Rules mentioned in synopses	"element" on page 54 "is fm table part element" on page 128 "reader" on page 145
General information on this topic	Developer Guide, Chapter 22, Translating Tables

start vertical straddle

Use the `start vertical straddle` rule inside the `element` rule for a table cell to specify that an occurrence of the cell element indicates the start of a vertical straddle.

Synopsis and contexts

```
element "gi" { . . .
    is fm table cell element ["fmtag"];
    reader start vertical straddle "name";
. . . }
```

Arguments

<i>gi</i>	A markup element's name (generic identifier).
<i>fmtag</i>	A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.
<i>name</i>	A name associated with a table straddle. This name must occur in at least one corresponding <code>end vertical straddle</code> rule.

Details

- Your DTD may contain elements that you want to format as tables in FrameMaker even though the element hierarchy does not match that required by FrameMaker for tables. In such a situation, the nature of the element hierarchy may indicate where vertical straddles should begin and end. The `start vertical straddle` rule allows you to specify such elements.
- Use this rule in conjunction with the `end vertical straddle` rule. That rule specifies a table cell or row that indicates the end of the vertical straddle started by this rule.
- You give a name to the particular straddle started by *gi*. In the corresponding `end vertical straddle` rule or rules, you use the same name to specify that the element ends this vertical straddle.

Examples

For an example of the use of this rule, see [Developer Guide, page 355: Creating parts of a table even when those parts have no content](#).

See also

Related rules	"start new row," (the previous section)
Rules mentioned in synopses	"element" on page 54 "is fm table part element" on page 128 "reader" on page 145
General information on this topic	Developer Guide, Chapter 22, Translating Tables

table ruling style is

You use the `table ruling style is` rule to specify the ruling style for all tables.

Synopsis and contexts

```
reader table ruling style is "style";
```

Arguments

style A ruling style for all tables. One of the keywords: None, Double, Medium, Thick, Thin, or Very Thin.

Details

- This rule specifies the ruling style applied to all tables. When working with the CALS table model, you can use the `frame`, `colsep`, and `rowsep` attributes to determine whether or not portions of a table have rulings. However, these attributes have boolean values. Consequently, you can only use them to say whether or not a table has a ruling, not what type of ruling to use if it does have one. In this situation, you could use the `table ruling style is` rule to set the ruling style for all tables.
- FrameMaker considers the ruling style set with this rule as custom ruling. If you re-import formats to the FrameMaker document and remove overrides, the ruling style set with this rule will remain. If possible, therefore, you should use table formats to specify ruling styles.

Examples

To specify that all tables should use the Thick ruling style, use this rule:

```
reader table ruling style is "Thick";
```

See also

General information [Developer Guide, Chapter 22, Translating Tables](#) on this topic

unwrap

Use the `unwrap` rule when you do not want to preserve an element on translation from one representation to another. If you specify that FrameMaker should unwrap an element (*gi* or *fmtag*), the software places the element's content as part of the content of the element's parent element, but does not make an element for *gi* or *fmtag* itself.

Synopsis and contexts

1. element "*gi*" **unwrap**;
2. fm element "*fmtag*" **unwrap**;

Arguments

gi A markup element's name (generic identifier).

fmtag A FrameMaker element tag. These names are case-sensitive and must appear in the rule the same as in the EDD.

Details

- When FrameMaker encounters an element to be unwrapped, it does not insert a corresponding element into the document it is creating. Instead, it inserts the content of an unwrapped element.
- If you use this rule to unwrap FrameMaker cross-reference elements or system variable elements, those elements become text in the resulting markup document.
- When importing a DTD or exporting an EDD, FrameMaker does not generate an element definition or declaration corresponding to an element that is unwrapped. Furthermore, when an element uses the unwrapped element in its definition, the software replaces the name of the unwrapped element with its content model or general rule in the general rule or content model of the element that used it or replaces it with the list of its children in an exception. You can change this behavior by using the `preserve fm element definition` rule.
- You cannot use the `unwrap` rule with any other subrule of the `element` or `fm element` rules. For example, you cannot specify that a markup element both be unwrapped and be translated to a FrameMaker element.

Examples

- A markup document used to produce both the student's and teacher's edition of a textbook might include an `ANSWER` element used for answers to exercises. In producing the teacher's edition of the textbook, this element might be unwrapped into FrameMaker as text. A structure API client could associate this element with the condition tag `Answer`.
- Suppose a DTD contains the following declarations:

```
<!ELEMENT wrapper - - (a, b)>
<!ELEMENT x - - (p, q, wrapper, r)>
<!ELEMENT y - - (#PCDATA) +(wrapper)>
```

and you have this rule:

```
element "wrapper" unwrap;
```

FrameMaker would generate the following element definitions:

Element (Container): X

General rule: P, Q, A, B, R

Element (Container): Y

General rule: <TEXT>

Inclusions: A, B

See also

Related rules ["preserve fm element definition" on page 140](#)
 ["drop" on page 51](#)

- Assume you have the same table as in the last example and you use this rule:

```
writer {
    use proportional widths;
    proportional width resolution is "8";
}
```

FrameMaker writes this start-tag for the table:

```
<table colwidth="1* 1* 2* 2* 2*">
```

See also

Related rules [“proportional width resolution is” on page 144](#)

General information [Developer Guide, Chapter 22, Translating Tables on this topic](#)

value

Use the `value` rule to translate the value of a markup attribute to the value of a particular FrameMaker property or to a particular choice for a FrameMaker choice attribute. The attribute’s declared value must be a name token group or `NOTATION` and a name token group.

Synopsis and contexts

1. **value** "*token*" *subrule*;
2. attribute "*attr*" { . . .
 value "*token*" *subrule*;
 . . . }
3. element "*gi*" { . . .
 attribute "*attr*" { . . .
 value "*token*" *subrule*;
 . . . } . . . }

Arguments

token A token in a name token group.

attr The name of a markup attribute.

gi A markup element’s name (generic identifier).

subrule One of the following:

`is fm value` translates a markup value to a particular choice for a FrameMaker choice attribute.

`is fm property value` translates a markup value to the value of a particular FrameMaker property.

Details

The rule can be used at the highest level to set a default, within a highest-level attribute rule to set the default for all attributes that use that token, or within an `element` rule to set the default for a particular token within a particular attribute in that element.

Examples

- To rename the FrameMaker `import by reference or copy` property as the `refcopy` attribute, and to also change the name tokens, use this rule:

```
attribute "refcopy" {
    is fm property import by reference or copy;
    value "r" is fm property value reference;
    value "c" is fm property value copy;
}
```

- If the token list (`r | b | g`) is used by multiple attributes, you can use these rules to translate the individual tokens consistently:

```
value "r" is fm value "Red";
value "b" is fm value "Blue";
value "g" is fm value "Green";
```

- If the token list (`r | b | g`) is used by several attributes as above, but by the `bird` element differently, you can add this rule to the above rules:

```
element "bird" {is fm element;
] attribute "species" {
    value "r" is fm value "Robin";
    value "b" is fm value "Blue Jay";
    value "g" is fm value "Goldfinch";
}}]
```

See also

Related rules	"is fm value" on page 131 "is fm element" on page 106
Rules mentioned in synopses	"attribute" on page 44 "element" on page 54
General information on this topic	Developer Guide, Chapter 20, Translating Elements and Their Attributes

value is

See “fm property” on page 78.

write structured document

By default, when you save a FrameMaker document to markup, the software writes out the document instance, any declarations for the internal DTD subset, and a `DOCTYPE` statement which references the external DTD subset, but (for SGML) not an SGML declaration nor the declarations within the external DTD subset. If an XML structure application (in `structapp.fm`) specifies a Schema file for output, that file is also written with the XML document. You can use this rule to confirm the default behavior.

Synopsis and contexts

```
writer write structured document;
```

ArgumentsNone.

Details

You cannot use the `write structure document` rule and the `write sgml document instance only` rule in the same read/write rules file.

See also

Related rules

- [“external dtd” on page 70](#)
- [“include dtd” on page 94](#)
- [“include sgml declaration” on page 96](#)
- [“write structured document instance only,” next](#)

write structured document instance only

By default, when you save a FrameMaker document to markup, the software writes out the document instance, any declarations for the internal DTD subset, and a `DOCTYPE` statement which references a file for the external DTD subset. For SGML, it does not write an SGML declaration. This rule causes the software to write the document instance only--no external or internal DTD, no Schema, and no SGML declarations.

Synopsis and contexts

```
writer write structured document instance only;
```

ArgumentsNone.

Details

- By default, when you translate a FrameMaker document to markup, as its last step the software runs the parser on the markup document to check its validity. If you use this rule, FrameMaker does not write a complete markup document and so does not send the result through the parser.
- You cannot use the `write structure document instance only` rule in the same read/write rules file as any of the `write structure document`, `include dtd`, or `include sgml declaration` rules.

See also

Related rules

- [“external dtd” on page 70](#)
- [“include dtd” on page 94](#)
- [“include sgml declaration” on page 96](#)
- [“write structured document,” \(the previous section\)](#)

writer

The `writer` rule indicates a rule that applies only on export of a FrameMaker document to markup. It can be used at the highest level to set a default or within an `element` rule to specify a subrule for that element.

Synopsis and contexts

1. `writer` { . . .
 subrule;
 . . . }
2. `element "gi"` { . . .
 writer { . . .
 subrule;
 . . . } . . . }

Arguments

gi A markup element’s name (generic identifier).

subrule Valid subrules:

`anchored frame` tells FrameMaker what to do with graphic elements other than those with a single non-internal FrameMaker facet. Allowed only within an `element` rule for a graphic element.

`character map` determines the correspondence between individual characters in the FrameMaker and markup character sets. Allowed only at the highest level.

`convert referenced graphics` tells the software to create new files for graphic files that were imported by reference. `drop content` exports a FrameMaker element without its contents. Allowed only within an `element` rule.

`equation` tells FrameMaker what to do with equation elements. Allowed only with an `element` rule for an equation element.

[`external dtd`](#) specifies an external DTD to use. Allowed only at the highest level.

`facet` tells FrameMaker what to do with a graphic element that has a single non-internal FrameMaker facet. Allowed only with an `element` rule for a graphic element.

[do not] [`include dtd`](#) specifies information to exclude or include in the written document. Allowed only at the highest level.

[do not] [`include sgml declaration`](#) specifies information to exclude or include in the written document. Allowed only at the highest level.

`line break` specifies treatment of line breaks not handled by the parser on export. Allowed at the highest level or within an `element` rule.

[do not] [`output book processing instructions`](#) specifies whether or not to create processing instructions that identify book components when writing a FrameMaker book as a markup document. Allowed only at the highest level.

`proportional width resolution is` specifies the total value to which proportional widths for table columns add up. Allowed only at the highest level.

`use proportional widths` specifies that the software should use proportional values in describing the widths of table columns. Allowed only at the highest level.

`write structured document` specifies that an entire SGML document should be written, not just the document instance. This is the default. Note that the external DTD subset is not written to the file. Instead, a DOCTYPE statement with a reference to the external DTD file is written. Allowed only at the highest level.

`write structured document instance only` specifies that only the document instance should be written, not the DTD and SGML declaration. Allowed only at the highest level.

Examples

- To tell FrameMaker not to use processing instructions to identify book components when writing a FrameMaker book as a markup document, use this rule:
writer do not output book processing instructions;
- Assume you want all graphics to be exported in TIFF format. Further assume that some of your graphic elements were imported from the TIFF format. For these elements you don't want to create a new external data entity. To accomplish this, use these rules:

```
element "graphic" {
  is fm graphic element;
  writer facet default{
    convert referenced graphics;
    export to file "$(entity) .tif as "TIFF";
    writer anchored frame
      export to file "$(entity).tif" as "TIFF";
  }
}
```

4

Conversion Tables for Adding Structure to Documents

You can set up a conversion table to help end users automate the task of adding structure to documents. The conversion table uses paragraph and character formats to identify which unstructured document objects to wrap in elements, and element tags to identify which child elements to wrap in parent elements. A user wraps all of a document's contents in one move by applying a structure command to the document and referring to one of your conversion tables.

This chapter describes how to set up a conversion table and define object and element mapping in it. For information on the commands for adding structure to documents, see the FrameMaker user's manual

How a conversion table works

A conversion table contains rules for mapping between document objects and elements and between child elements and parent elements. The table is a regular FrameMaker table, with at least three columns and one body row. Each body row holds one rule.

The first column in a conversion table specifies a document object, a child element, or a sequence of child elements or paragraphs to wrap in an element. A *document object* is a paragraph, text range, table, table part (such as heading or row), equation, variable, footnote, Rubi group, Rubi text, marker, cross-reference, text inset, or graphic (anchored frame or imported graphic object).

The second column in the table specifies the element in which you want to wrap the object, child element, or sequence. The third column can specify an optional *qualifier* to use as a temporary label for the element in rules that are applied later. For example:

Wrap this object	In this element	With this qualifier
P:BulletItem	Item	Bullet
E:Item[Bullet]+	BulletList	

The first column uses a one-letter code and usually a tag to identify an object or element.

The second column specifies the element in which to wrap the object or element.

The third column can provide a label for the new element to be used in later rules.

To add structure to a document or book, an end user chooses the **Structure Current Document...**, **Structure Documents...**, or **Structure Current Book...** command from the **StructureTools > Utilities** submenu and refers to one of the conversion tables.

When you add structure to a document manually, you typically begin with the lowest-level components and work up to the highest level. For example, to add structure to a chapter you might start by wrapping sub-paragraph objects like text ranges and tables, then wrap the contents of paragraphs together in `Paragraph` elements, then wrap sequences of `Head` and `Paragraph` elements in `Section` elements, and so on until the entire document is wrapped in a single highest-level `Chapter` element.

The process of adding structure with a conversion table is similar to adding structure manually. FrameMaker begins by applying rules to document objects below the paragraph level, then applies rules at the paragraph level, and proceeds through successively higher levels. The process stops when FrameMaker reaches a single highest-level element or when no more rules can be applied. To understand this process, it helps to have manually structured a document.

Using the sample table above, FrameMaker first wraps each paragraph with the paragraph format `BulletItem` in an element called `Item` and gives the element a qualifier called `Bullet`. Then it wraps each `Item` element with the qualifier `Bullet` in a parent element called `BulletList`.

FrameMaker tries to order the rules as much as possible. If a rule needs a building block that is generated by a later rule, the later rule is run first so that all of the building blocks in the first rule are available. To make a conversion table easy to interpret for a human reader, you may want to write the rules in the order they should be applied.

Setting up a conversion table

You can have FrameMaker generate an initial conversion table for you from an unstructured document or book, or you can create a conversion table entirely from scratch. If you already have a document that end users need to add structure to, or a document that is similar to one users will add structure to, you'll probably want to let FrameMaker generate the initial table. You can modify the rules in the table as necessary.

After creating a conversion table, you can update it from other unstructured documents. Updating a table adds rules for any objects in the document that are not yet in the table.

A conversion table document can include the conversion table itself (which may be split up into several tables) and text or graphics you want to include for documenting the rules. It cannot have any tables other than conversion tables. You need to save the document before it can be used for adding structure to other documents or books.

Each body row in a conversion table holds one mapping rule. FrameMaker reads only the information in the first three columns of the body rows, so you can use additional columns and headings and footings for comments about rules.

For information on defining and modifying the rules in a table, see [“Adding or modifying rules in a conversion table” on page 167](#).

Generating an initial conversion table

You can have FrameMaker generate a conversion table from an unstructured document. This is the easiest way to begin a new conversion table.

To generate an initial conversion table, choose **Generate Conversion Table** from the **StructureTools** menu in a document with objects you want to structure. Select **Generate New Conversion Table** in the dialog box and click **Generate**.

The software looks through the flows on body pages in the document and compiles a list of every object that can be structured. For each object, it gives the object type and the format tag used in the document (if the object has a format), and maps the object to an element. The element tag is the same as the format tag, or if the object does not have a format, the element tag is a default name such as `CELL` or `BODY`. If necessary, FrameMaker removes parentheses and other characters to create an element tag that is valid.

The initial conversion table gives you a first pass through the document, identifying objects to wrap in elements. It does not identify child elements to wrap in parent elements—you need to add those rules to the table yourself.

This is an example of an initial conversion table:

Wrap this object	In this element	With this qualifier
P:Head1	Head1	
P:Head2	Head2	
P:Body	Body	
P:Code	Code	
SV:Current Date \(\Long\)	CurrentDateLong	
C:Code	cCode	
TC:	CELL	
TR:	ROW	

For details on the object type identifiers used in the table (such as `P:` and `TC:`), see [“Identifying a document object to wrap” on page 169](#).

Note that if there are conflicts in a format tag from the unstructured document, an object type identifier in lowercase is prepended to any duplicate element tag. In the example above, the

element tag for text ranges with the `Code` character format is `cCode` because the document also has a paragraph format called `Code`.

When you create an initial table, FrameMaker does not examine the document's format catalogs—it looks only at objects actually used in the document. For this reason, the table may not be as complete as you need. You may want to update the table from a set of documents that together provide all or most of the objects you need rules for. You can also add and modify rules manually.

The initial conversion table does not contain a root element for the structure hierarchy, but you can add one manually, using the tag `RE:RootElement`, so that documents you convert using the table will have a “well formed” structure in which all elements are children of the root element. See [“Specifying the root element for a structured document” on page 168](#).

The initial conversion table does contain elements for all defined paragraph and character formats that are used in the unstructured document, and for all objects, including cross references, markers, footnotes, equations, graphics, system variables, and tables. Formatting is retained in the structured document created from the table, and carried forward into the EDD in `ParagraphFormattingTag` elements.

If the original document contains format overrides or unnamed formats applied directly to text, you can create named formats from them before conversion, or flag them for manual update in the conversion table. See [“Flagging format overrides” on page 176](#) and [“Wrapping untagged formatted text” on page 176](#).

Setting up a conversion table from scratch

You can set up a regular FrameMaker table to serve as a conversion table. The table must appear on a body page in its own document. The document and table can be structured or unstructured. Begin a conversion table this way if you do not yet have an unstructured document to use for generating the table.

To set up a conversion table from scratch, create a new document and insert a table with at least three columns and one body row. The table can have any number of heading or footing rows.

You can divide a conversion table into several smaller tables. This is helpful when you have many rules and want to organize the rules in groups. Each table must have at least three columns and one body row. You can add explanatory heads and paragraphs between the tables to document the rules. Do not include tables that are not conversion tables.

Updating a conversion table

After creating a conversion table, you may want to update the table from at least one other unstructured document to get a more complete list of objects. FrameMaker adds a rule for each object from the document that is not already listed in the table.

To update a conversion table, choose **Generate Conversion Table...** from the **StructureTools** menu in a document with the objects you want to structure. Select the name of the conversion table document in the **Update Conversion Table** popup menu and click **Generate**.

When you update a conversion table, the process that FrameMaker goes through is similar to the process of generating an initial table. The software does not examine the document's format catalogs—it looks only at objects actually used in the document.

Adding or modifying rules in a conversion table

Each body row in a conversion table holds one mapping rule. Follow these steps to define a mapping rule:

1. In the first column, identify a document object, a child element, or a sequence of child elements or paragraphs to wrap.

You use a one- or two-letter code to identify the type of item and, in most cases, a format or element tag to narrow the definition. See [“Identifying a document object to wrap” on page 169](#), [“Identifying an element to wrap” on page 170](#), or [“Identifying a sequence to wrap” on page 171](#).

2. In the second column, specify an element in which to wrap the object, child element, or sequence.

Type one valid element tag. If you are writing rules for a document that already has element definitions, use tags from the document's Element Catalog.

If you are wrapping a table part, graphic, or inset, FrameMaker always wraps all instances of the object in the same kind of element. The element has a default tag, such as `CELL`, `BODY`, `GRAPHIC`, or `INSET`. Type a different tag in the second column only if you want to override the default tag.

You can also give an element an attribute with a value. For details, see [“Providing an attribute for an element” on page 173](#).

3. (Optional) In the third column, add a qualifier for the new element tag.

A qualifier is a temporary label that you can attach to an element tag for the structuring process. If you wrap the element in a parent element in a later rule, you include the qualifier tag with the element tag. For details, see [“Using a qualifier with an element” on page 173](#).

To make a conversion table easy to read and to help you think through the process, we recommend that you put the rules in order from the lowest level to the highest. In the first rows of the table, write rules that wrap individual document objects such as text ranges, tables, and paragraphs; next add rules that wrap child elements in parent elements; then add rules that wrap sequences in elements; and finally add rules that wrap elements in one root element.

Every flow in a document must have a highest-level element, and the element can be different for each flow.

About tags in a conversion table

Format and element tags in a conversion table are case-sensitive and must be specified the way they are defined in their catalogs. Qualifier tags are also case-sensitive, and two occurrences of

one qualifier must match exactly. The following characters are not allowed in an element tag, but can appear in a format or qualifier tag if you precede them with a backslash (\) in the table:

() & | , * + ? % [] : \

A space character does not need to be preceded with a backslash. For example, you can write the tag `Format A`.

You can use a percentage sign (%) as a wildcard character in a format or element tag to match zero, one, or more characters. For example, `P:%Body` matches paragraphs with the format tag `Body`, `FirstBody`, or `BulletBody`.

Specifying the root element for a structured document

FrameMaker now allows you to specify a *root element*, the highest valid element in a document, so that the converted document adheres to structured document convention.

To do so, specify the optional `RE:RootElement` after conversion. You must add it manually to the conversion table, specifying the tag itself, `RE:RootElement`, in the first column, and the element name that you choose in the second column.

When you generate a structured document using this manually modified conversion table, the resulting document contains a well-formed hierarchy with a valid root element. If you convert an entire book using the table, each document contains a valid root element.

The root element name that you choose should be unique within the document. If you specify a name that its being already defined for some other object, the root element is ignored. You can still generate a structured document with the table, but it will not have a valid root element, and a message is added to the FrameMaker Log window: "Element name defined in second column of conversion table for root element is not unique. Root element ignored."

The root element tag should appear only once in the conversion table. If it appears anywhere else with a different name, it is ignored and a generated document does get a root element, but if it appears twice with the same name, both elements are ignored and a generated document will have no root element.

If no root element is generated for a document (either because the conversion table contains no `RE:RootElement` tag or because it is not specified correctly), the 'NoName' element appears at the top of the element hierarchy. The rest of the elements are its children, and the hierarchy is shown to have an invalid structure.

The `RE:RootElement` is particularly useful for unstructured documents that do not easily conform to the required structure rules, maybe due to poor adherence to tagging rules or too many manual style overrides. In these cases it may be uneconomic to tailor your conversion table for every possible formatting variation.

Identifying a document object to wrap

To identify a document object to wrap in an element, type an object type identifier and (optionally) a format tag in the first column of the table. Separate the identifier and format tag with a colon.

FrameMaker finds all the objects with that type and format and wraps them in the element you specify in the second column of the table. If you leave the format tag out of the rule, FrameMaker finds all the objects with the specified type that are not identified in other conversion rules.

For example:

Wrap this object	In this element
P:Body	Para
T:RulesTbl	RulesTbl
T:	StandardTbl
Q:Small	SmallEqns

This rule wraps all tables not named in other rules, regardless of format tag.

These are the object type identifiers and format tags you can use:

Object type	Identifier	Format tag
Paragraph	P:	Paragraph format tag
Text range	C:	Character format tag
Table	T:	Table format tag
Table title	TT:	(none)
Table heading	TH:	(none)
Table body	TB:	(none)
Table row	TR:	(none)
Table cell	TC:	(none)
System variable	SV:	Variable format name
User variable	UV:	Variable format name
Graphic (anchored frame or imported object)	G:	(none)
Footnote	F:	Location of footnote: Table or Flow
Rubi group	RG:	(none)
Rubi text	R:	(none)
Marker	M:	Marker type

Object type	Identifier	Format tag
Cross-reference	X:	Cross-reference format name
Text Inset	TI:	(none)
Equation	Q:	Size of equation: Small, Medium, or Large

Table parts, graphics, and text insets do not have any formatting information, so FrameMaker wraps all instances of those objects in the same kind of element. The element has a default tag, such as `CELL`, `BODY`, `GRAPHIC`, or `INSET`. (Specify a different tag in the second column to override the default tag.)

You can write identifiers and the keywords for footnote location or equation size in any combination of uppercase and lowercase letters. The names of formats and marker types are case-sensitive, however, and must be typed the way they are specified in their catalogs.

A system variable can be wrapped in a variable element but a user variable cannot. If you identify a user variable, FrameMaker wraps it in a container element with the tag specified in the second column.

FrameMaker wraps a text inset in a container.

Identifying an element to wrap

To identify a child element to wrap in a parent element, type the object type identifier `E`: followed by an element tag and (optionally) a qualifier in brackets in the first column of the table. The qualifier must already be defined for the element in a rule applied earlier.

FrameMaker finds all instances of the element and wraps them in the element you specify in the second column of the table. You can omit the element tag if you include a qualifier.

For example:

Wrap this object	In this element
E:Item[Bullet]	BulletItem
E:[1Head]	ChapHead

This rule wraps all elements with the qualifier `1Head` not named in other rules.

You can type the `E`: identifier in either uppercase or lowercase. The element tags are case-sensitive, however, and must be typed the way they are specified in their catalog. You can even omit the `E`: identifier—when FrameMaker reads an object name with no identifier, it assumes the object is an element.

To identify a table child element to wrap in a table parent element, type the object identifier `TE`: followed by `E`: , an element tag, and (optionally) a qualifier in brackets in the first column of the

table. This allows you to name a table element from one or more child elements, rather than naming it from a table format tag (with the `T:` identifier).

For example:

Wrap this object	In this element
TB:RulesBody	RulesBody
TE:E:RulesBody	RulesTbl

This rule wraps RulesBody table child elements in a RulesTbl table element.

Most often, you wrap multiple elements together in one parent. You can use `E:` or `TE:` to identify a sequence of elements for this. For more information, see [“Identifying a sequence to wrap,”](#) next. For more information on qualifiers, see [“Using a qualifier with an element”](#) on page 173.

Identifying a sequence to wrap

You can wrap a sequence of child elements in a parent element. For example, you might wrap a `Head` element followed by one or more `Paragraph` and `List` elements in a higher-level `Section`.

You can also wrap a sequence of unwrapped paragraphs in an element. For example, you might wrap a sequence of paragraphs with the format tag `Body` all in one `Note` element. (With other unwrapped document objects such as tables, graphics, and text ranges, you can wrap only one object in an element.)

To identify a sequence to wrap, specify object type identifiers and element tags or paragraph format tags, and use symbols to further describe the sequence. You can mix elements and unwrapped paragraphs together in one specification.

These are the symbols you can use:

Symbol	Meaning
Plus sign (+)	Item is required and can occur more than once.
Question mark (?)	Item is optional and can occur once.
Asterisk (*)	(SGML only) Item is optional and can occur more than once.
Comma (,)	Items must occur in the order given.
Ampersand (&)	Items can occur in any order.
Vertical bar ()	Any one of the items in the sequence can occur.
Parentheses	Beginning and end of a sequence.

The symbols available are the same connectors, occurrence indicators, and parentheses used in general rules in an EDD. For more information on the symbols, see [“Writing an EDD general rule” on page 175](#).

For example:

To identify this sequence	Use this specification
One or more <code>Item</code> elements	<code>Item+</code>
An element tagged <code>Item[Bullet]</code> followed by one or more unwrapped paragraphs tagged <code>Bullet</code>	<code>E:Item[Bullet], P:Bullet+</code>
A <code>ChapNum</code> element followed by a <code>ChapName</code> element	<code>ChapNum, ChapName</code>
A <code>Head</code> element followed by zero or more <code>Paragraph</code> , <code>BulletList</code> , or <code>NumberList</code> elements	<code>Head, (Paragraph BulletList NumberList)*</code>
An <code>Item[FirstNItem]</code> element followed by one or more <code>Item[NItem]</code> elements	<code>Item[FirstNItem], (Item[NItem])+</code> or <code>[FirstNItem], ([NItem])+</code>
A <code>RulesTitle</code> table title element followed by a <code>RulesBody</code> table body element	<code>TE:E:RulesTitle, E:RulesBody</code>

Strict or loose sequence specification

If you already have a well defined or standard based application structure, you may try to use the general rule specification as it is defined in your EDD. In many cases, with well formatted unstructured documents, you will achieve excellent conversion results. However, in practice unstructured documents often break the rules. You will find incorrect tagging, manual formatting overrides and other non-standard features.

Your strict conversion table will not cope well with these source documents. It will fail to wrap sequences that do not match a strict specification. You can avoid these problems by providing a less restrictive sequence specification.

The revised sequence specification must be compatible with the required structure for example if the EDD specified this general rule:

`Head, Para+, Table?, Graphic?, Section*`

The strict sequence specification could be identical. However, if the conversion table encountered a document which no `Head` element or a `Para` between `Table` and `Section`, the entire sequence will not be wrapped. The revised sequence specification could be:

`Head?, (Para | Table| Graphic)*, Section*`

This will give the correct conversion when the source document is well tagged but will also cope with a wide range of variations.

Providing an attribute for an element

When you specify an element in the second column of the table, you can provide an attribute for the element. In the structured document, all the element instances will have the attribute name and value.

To provide an attribute for an element, type the attribute name and value in brackets after the element tag in the second column of the table. Separate the name and value with an equal sign, and enclose the value in double quotation marks.

For example:

Wrap this object	In this element
P:Intro	Para[Security="Unclassified"]
P:Important	Note[Label="Important"]
E:Item+	List[Type="Numbered"]

If the unstructured document has an Element Catalog with an element and attribute matching the one you're providing, the attribute is the type specified in the catalog. If the attribute does not match an attribute already defined, the type is string.

If you need to use a double quotation mark in an attribute value, escape the quotation mark with a backslash (\). Other restrictions on characters are determined by the attribute's type. (The string type allows any arbitrary text string.) For information on these restrictions, see ["Attribute type" on page 192](#).

To give an element more than one attribute, separate the attribute definitions with an ampersand (&). For example, this specification gives the element a `Type` attribute with the value `Numbered` and a `Content` attribute with the value `Procedure`:

```
List [Type="Numbered" & Content="Procedure"]
```

For an example of an attribute that maintains formatting information from a qualifier, see ["Using a qualifier with an element," next](#).

Using a qualifier with an element

Qualifiers act as temporary labels that preserve formatting information from the unstructured document until all elements have been wrapped. Qualifiers are used only in the conversion table—they do not show up in a final structured document.

To use a qualifier with an element specified in the second column of the table, type the qualifier tag in the third column. Then when you wrap the element in a later rule, type the qualifier tag in brackets after the element tag in the first column. Spell and capitalize the qualifier the same way

in the two places. FrameMaker keeps track of qualifiers separately from elements, so you can use the same tag for an element and its qualifier.

For example:

Wrap this object	In this element	With this qualifier
P:BulletItem	Item	bulleted
P:NumberItem	Item	numbered
E:Item[bulleted]+	BulletList	
E:Item[numbered]+	NumberList	

First specify the qualifier for the element. —

— Then include the qualifier with the element in later rules.

In the example above, an unstructured document has both bulleted items and numbered items, with paragraph formats called `BulletItem` and `NumberItem`. When adding structure to the document, you want to wrap all the items in an `Item` element with a parent element of either `BulletList` or `NumberList`. To do this, you need to keep the `BulletItem` and `NumberItem` formatting designations long enough to determine in which list to wrap the items. The conversion table first associates qualifiers called `bulleted` and `numbered` with new `Item` elements. Then it wraps each `Item` element in either a `BulletList` or a `NumberList`, as specified by its qualifier.

Note that if you specify an attribute for formatting information in the second column, you cannot use the attribute as a label for preserving formatting during the conversion process. You still need to use the qualifier. For example:


Wrap this object	In this element	With this qualifier
P:BulletItem	Item	bulleted
P:NumberItem	Item	numbered
E:Item[bulleted]+	List[Type="Bulleted"]	
E:Item[numbered]+	List[Type="Numbered"]	

Handling special cases


You may need to accommodate a few special circumstances or requirements in a conversion table.

Promoting an anchored object

In an unstructured FrameMaker document, a table or an anchored graphic must be anchored in a paragraph. The anchor specifies which paragraph to keep the object with as an author continues to edit the document. When a user adds structure to the document, the table or graphic normally becomes a child of the paragraph with the anchor, like this:



In a structured document, you often want a table or graphic element to be at the same level as its surrounding paragraph elements. FrameMaker can break the table or graphic out of its paragraph and promote the element to be a sibling of the paragraphs, like this:



To break a table or graphic out of its paragraph and promote it one level, add the keyword `promote` in parentheses after the element tag for the table or graphic. (The keyword is not case-sensitive.) For example:

Wrap this object	In this element
T:Table	Table (promote)

Note that FrameMaker promotes the object at the location of the anchor symbol in the paragraph. If the symbol is in the middle of the paragraph, the structured document will have half of the paragraph, then the table, and then the other half of the paragraph. Typically, you want the symbol to be at the end of the paragraph.

Flagging format overrides

An unstructured document may have *format overrides*. This happens when someone uses the Paragraph or Character Designer to make formatting changes to a paragraph or text range but does not save the changes in the catalog format.

When an end user adds structure to a document, FrameMaker does not normally identify format overrides. You can have FrameMaker flag all element instances in the document that have overrides so that the user can find the overrides and decide how to handle them in a structured context.

To flag format overrides, add the rule `flag paragraph format overrides` or `flag character format overrides` to the first column of the table. (The rule is case-insensitive.) This is a general instruction for the table, so you do not add anything to the second and third columns. For example:

Wrap this object	In this element
flag paragraph format overrides	
flag character format overrides	

At each element instance that has an override in the document, FrameMaker adds an attribute called `Override` with the value `Yes`.

Note: Use the FrameMaker utility "Create and Apply Formats" before conversion to turn format overrides and untagged formatted text into named paragraph and character formats, which can be carried forward automatically into the structured document and EDD.

Wrapping untagged formatted text

It is possible for someone to format a text range by applying commands from the Font, Size, and Style submenus in the Format menu—and not use a character format at all. This leaves the text formatted but without a tag that you can refer to in your conversion table.

You can have FrameMaker find text that has been formatted with the submenu commands and wrap it in a "catch-all" element. After adding structure to a document, the end user will probably

want to look at these instances and change them to other elements (such as `Emphasis`) that more specifically describe the type of formatting.

To wrap untagged formatted text, add the rule `untagged character formatting` to the first column of the table and add an element to the second column. (The rule is case-insensitive.) For example:

Wrap this object	In this element
untagged character formatting	UntaggedText

This might also be useful while you are developing a conversion table. You can add structure to a sample document with this rule to see if the document has any untagged formatting.

Note: Use the FrameMaker utility "Create and Apply Formats" before conversion to turn format overrides and untagged formatted text into named paragraph and character formats, which can be carried forward automatically into the structured document and EDD.

Nesting object elements

Typically, a non-paragraph object such as a table or graphic is wrapped in an object element and then wrapped in a paragraph element. You can also wrap the object in more than one level below the paragraph. Sometimes you need to do this to conform to a DTD that requires more hierarchy, or you may just want to be able to use two objects together.

To nest object elements in a paragraph, define each mapping in a separate rule in the table. For example:

Wrap this object	In this element
M:Index	Index
G:	Graphic
E:Index & E:Graphic	Figure

In the example above, the rules wrap an index marker in an `Index` element and a graphic anchor in a `Graphic` element, and then they wrap the two elements together in a `Figure` text range element. This way, the graphics in a structured document will automatically have a marker identifying a location to be included in an index.

Building table structure from paragraph format tags

When FrameMaker adds structure to tables, it normally wraps all instances of a table part in the same kind of element and uses a default name for the element, such as `CELL`, `ROW`, `HEADING`, or `BODY`. You can override the default name by providing a different element tag in the second column of the conversion table.

If you want to have more than one kind of element for a particular table part, you can build the structure up from the format tags used in the cells or titles. This allows you to distinguish between different formatting used in different instances of a single table part. For example, a table may have a few special body rows with italicized text that marks divisions in the table. Or a table may have two titles, one of them a subtitle in a different font size.

To build table structure from paragraph format tags, for each cell or title rule use the `TC:` or `TT:` type identifier followed by the `P:` identifier and a format tag in the first column of the table. For example:

Wrap this object	In this element
TC: P:DividerCell	DividerCell
TC: P:BodyCell	BodyCell
TR:DividerCell+	ROW
TR:BodyCell+	ROW
TB:Row+	BODY

In the example above, the rules map cells that use a `DividerCell` paragraph format in an element called `DividerCell` and map cells that use a `BodyCell` paragraph format in an element called `BodyCell`. Then they wrap both kinds of cell elements in the same default `ROW` element and continue the wrapping normally.

Testing and correcting a conversion table

You should test and correct a conversion table as you develop it. To do this, prepare a sample document that represents the type of documents the table will apply to, and use the conversion table to add structure to the sample. Make sure your sample document has all of the document objects that the final documents may contain.

When a structure command reads a conversion table, it identifies any syntax errors in the rules and displays the errors in a log file. Correct the table and test it again until no more errors are found.

You may find it helpful to wrap only document objects for your first testing pass, without wrapping in higher levels of hierarchy. When you're sure that the rules for wrapping individual

objects are correct, start writing and testing the rules to wrap elements and sequences in parent elements.

5

CSS to EDD Mapping

This chapter provides a reference for the CSS to EDD mapping feature, grouped by CSS property category. Each property's description includes the following headings.

CSS property The CSS 2.0 property name

CSS Property Values A simple list of the available property values.

Mapped to EDD property Shows the element name of the equivalent EDD formatting property. For table parts it shows the mapping for EDD table parts.

Comments/Values Additional information about the mapping includes EDD element property values.

While importing a Cascading Style Sheet (CSS) into an EDD, any property or selector in the CSS that cannot be mapped to an equivalent EDD rule is ignored by FrameMaker. No error log is displayed and errors in the CSS file are not reported.

The EDD does not support all properties and selectors defined in CSS 2.0. While importing a CSS into an EDD, FrameMaker will ignore any unsupported properties or selectors.

CSS Font Properties

Fonts are mapped as in the following table:

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
font-family	font-family family-name generic-family	PropertiesFont < Family element.	Font Set is not supported. <ul style="list-style-type: none">• Generic-Family can't be supported.• Only one font-family can be specified using the EDD Family element.

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
font-size	<p>length in units</p> <ul style="list-style-type: none"> • cm (centimeters) • ex (exs) • in (inches) • mm (millimeters) • pc (picas) • pt (points) • px (pixels) <p>% (percentage)</p> <p>Relative size with these values:</p> <ul style="list-style-type: none"> • larger • smaller <p>Absolute size with value of:</p> <ul style="list-style-type: none"> • xx-small • x-small • small • medium • large • x-large • xx-large 	<p>PropertiesFont < Size element.</p> <p>Not supported</p> <p>PropertiesFont < Size element.</p>	<p>Only font-size with a length in points is recognised, all other length types are ignored and the</p> <p>% values are not mapped as FrameMaker does not calculate relative values proportionally.</p> <p>The corresponding absolute values in FrameMaker are mapped as follows:</p> <ul style="list-style-type: none"> • xx-small = 7.0pt • x-small = 8.4pt • small = 10pt • medium = 12pt (Default) • large = 14.4pt • x-large = 17.3pt • xx-large = 20.8pt
font-style	normal italic oblique	<p>PropertiesFont < Angle with Regular or Italic child elements.</p> <p>CSS oblique is mapped to EDD Italic.</p>	
font-variant	normal small-caps	<p>CSS small-caps is mapped to EDD PropertiesFont < Case < SmallCaps.</p> <p>No action for normal.</p>	

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
font-weight	normal bold bolder lighter 100 200 300 400 500 600 700 800 900	PropertiesFont < Weight. CSS normal and bold are mapped to Regular and Bold All weights <= 400 are mapped to Regular, and > 400 are mapped to Bold.	Relative values bolder and lighter cannot be mapped as FrameMaker does not calculate relative values.
font	font-style font-variant font-weight font-size line-height font-family caption icon menu message-box small-caption status-bar	As listed for the individual CSS properties above.	caption, icon, menu, message-box, small-caption and status-bar fonts are not supported.
font-stretch	normal ultra-condensed condensed semi-condensed semi-expanded expanded extra-expanded ultra-expanded wider narrower	PropertiesFont < Stretch. PropertiesFont < StretchChange.	The mappings from CSS to FrameMaker EDD are: <ul style="list-style-type: none"> • ultra-condensed = 50 • extra-condensed = 60 • condensed = 72 • semi-condensed = 86 • normal = 100 • semi-expanded = 120 • expanded = 144 • extra-expanded = 173 • ultra-expanded = 207 • wider = +20 • narrower = -20
font-size-adjust	number none		@font-face is not supported.

CSS text properties

The CSS text properties are mapped as in the following table:

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
text-decoration	underline	PropertiesFont < Underline element.	
	overline	PropertiesFont < Overline element.	
	line-through	PropertiesFont < Strikethrough element.	
	blink	Blink is not supported.	
text-transform	uppercase	PropertiesFont < Case < Uppercase element.	Both text-transform and font-variant map to the Case element of EDD. If both these properties are used for an element context, then only the text-transform value is used.
	lowercase	PropertiesFont < Case < Lowercase element.	
	capitalize	capitalize is not supported.	
text-align	left right center justify string	PropertiesBasic < PgfAlignment. CSS left, right, center and justify are mapped to EDD Left, Right, Center, and Justified respectively. CSS string is not supported.	
text-indent	length percentage	PropertiesBasic < Indents < FirstIndent percentage value is not supported.	
line-height	number length percentage	Not supported	
word-spacing	normal length inherit	PropertiesAdvanced < WordSpacing. The CSS length value maps to the EDD minimum value.	In the EDD, WordSpacing accepts percentage values of the font's em space. Therefore, only an em value of CSS word-spacing can be mapped to EDD.

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
letter-spacing	normal length inherit	PropertiesAdvanced < LetterSpacing.	In the EDD, LetterSpacing can have a value of "yes" or "no". A positive value for CSS length maps to "yes" in the EDD.
text-shadow		Not supported	
white-space		Not supported	

CSS color and backgrounds properties

The CSS color and background properties are mapped as in the following table:

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
color	name rgb	PropertiesFont < Color	<ul style="list-style-type: none"> If the name of color is specified and that color is not defined in FrameMaker (CSS includes 16 predefined color names), a new color is created with that name and is assigned the value, <code>rgb</code>. If the <code>rgb</code> value of the color is specified, a new color name is created with that value.
background-color		Not supported	
background-image		Not supported	
background-attachment		Not supported	
background-position		Not Supported	
background-repeat		Not Supported	

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
background	background-color background-image background-repeat background-attachment background-position	Not Supported	

CSS Formatting Model

The CSS Box Model and Formatting Model are mapped as in the following table:

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
margin-right	length percentage auto	PropertiesBasic < Indents < RightIndent.	The percentage value is not supported.
margin-left	length percentage auto	PropertiesBasic < Indents < FirstIndent and LeftIndent.	The percentage value is not supported.
margin-top	length percentage auto	PropertiesBasic < Indents < SpaceAbove.	The percentage value is not supported.
margin-bottom	length percentage auto	PropertiesBasic < Indents < SpaceBelow.	The percentage value is not supported.
margin	margin-right margin-left margin-top margin-bottom	As listed for the individual CSS properties above.	
border, border*		Not supported	

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
padding, padding*		Not supported	
width		Not supported	
height		Not supported	
min-width		Not supported	
min-height		Not supported	
max-width		Not supported	
max-height		Not supported	
float	left	PropertiesPagination < Placement < SideHead < Left	The main flow in the target structured document must have "room for side head" enabled to acheive the expected result.
	right	Not supported	
clear		Not supported	

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
display	inline	CSS <code>inline</code> elements are supported by using the <code>TextRangeFormatting</code> element.	<ul style="list-style-type: none"> When CSS <code>inline</code> is specified all CSS properties that map to EDD <code>PropertiesFont</code> child elements are retained. All other CSS properties are ignored. The default behaviour of CSS <code>inline</code> is equivalent to a FrameMaker text range. The default behaviour of CSS <code>block</code> is equivalent to a FrameMaker paragraph. If there are two different rules for a single element in which one of the selectors is more specific than the other, and both rules specify the display property with a different value, then in FrameMaker the final value of the display property is undefined, and the corresponding element type in the EDD is also undefined.
	block	CSS <code>block</code> elements are supported by using the <code>ParagraphFormatting</code> element.	
	run-in	<code>PropertiesPagination</code> < <code>Placement</code> < <code>RunInHead</code> element	
	compact	<code>PropertiesPagination</code> < <code>Placement</code> < <code>SideHead</code> element	
	list-item	<code>PropertiesNumbering</code> < <code>AutoNumFormat</code>	

CSS Pagination Properties

The CSS Pagination properties are mapped as in the following table:

CSS property	CSS Property Values	EDD property	Comments/Values
page-break-before	auto always avoid left right inherit	PropertiesPagination < StartPosition CSS to EDD element mapping:	
		<ul style="list-style-type: none"> • always = TopOfpage • left = TopOfLeftPage • right = TopOfRightPage. 	
		The avoid property is not supported.	
page-break-after		Not supported	
page-break-inside		Not supported	
widows/orphans	integer inherit	PropertiesPagination < WidowOrphanLines	In CSS, widows and orphans are different properties and hence they can have different values. But, in the EDD, a single element, WidowOrphanLines, controls both values, and hence they have the same value.
marks@page	crop cross	Not supported	
		Not supported	An EDD has no control over the page layout. In FrameMaker page layout is designed into the structured template.
page		Not supported	To achieve the required result set up a suitable ApplyMasterPages command. See the Using Adobe® FrameMaker® 9 guide.
size	length auto portrait landscape inherit		An EDD has no control over the page layout. In FrameMaker page layout is designed into the structured template.

CSS generated content, automatic numbering, and lists

The CSS generated content, automatic numbering, and lists are mapped as in the following table:

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
list-style-type	<ul style="list-style-type: none"> • disc • circle • square • decimal • decimal-leading-zero • lower-roman • upper-roman • lower-alpha • upper-alpha • lower-latin • upper-latin • lower-greek • hebrew • armenian • georgian • cjk-ideograph • hiragana • katakana • hiragana-iroha • katakana-iroha • none 	Not supported	This CSS property is not supported in EDD. We have to enhance EDD for this.
list-style-image		Not supported	
list-style-position		Not supported	
list-style	list-style-type, list-style-image, list-style-position	Not supported	

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
content	string	The text content of the <code>Prefix</code> or <code>Suffix</code> element.	string, <code>attr(AttributeName)</code> , <code>open-quote</code> and <code>close-quote</code> may be used in any combination as required. Separate each item with whitespace. <ul style="list-style-type: none"> • To create a <code>Prefix</code> use the CSS <code>:before</code> psuedo element selector • To create a <code>Suffix</code> use the CSS <code>:after</code> psuedo element selector • In CSS, the string generated by the <code>content</code> property can have any CSS style. In contrast, EDD <code>Prefix</code> and <code>Suffix</code> rules can have only use font formatting (through the <code>PropertiesFont</code> element).
	<code>attr(AttributeName)</code>	<code><\$attribute[AttributeName]></code>	
	<code>open-quote</code>	"	
	<code>close-quote</code>	"	
	<code>counter</code>	Not supported	
	<code>uri, quotes</code>	Not supported	
<code>counter-increment</code>		Not supported	
<code>counter-reset</code>		Not supported	
<code>counter</code>		Not supported	
<code>counters</code>		Not supported	
<code>marker</code>		Not supported	
<code>marker-offset</code>		Not supported	
<code>White-space</code>		Not supported	
<code>position</code>		Not supported	
<code>z-index</code>		Not supported	
<code>visibility</code>		Not supported	

CSS Tables

Container is the default element type in an EDD. An element can be specified in CSS as a `table component` or `table component group` using the `display` property. If an element is a `Container` in the EDD but the CSS specifies the element as `Table/table-Tow`, then the element type in EDD is changed from `Container` to the corresponding table element type.

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
<code>display</code>	<code>table</code>	Element < Table	<ul style="list-style-type: none"> FrameMaker table part elements cannot have <code>PrefixRules</code> or <code>SuffixRules</code>. So, a rule with the <code>:after</code> or <code>:before</code> pseudo element selector, is ignored. FrameMaker table part elements cannot have <code>TextRangeFormatting</code> element in the EDD. So, the <code>inline</code> value of the <code>display</code> property is ignored.
	<code>table-inline</code>	Not supported	
	<code>table-row</code>	Element < TableRow	
	<code>table-row-group</code>	Element < TableBody	
	<code>table-header-group</code>	Element < TableHeading	
	<code>table-footer-group</code>	Element < TableFooting	
	<code>table-cell</code>	Element < TableCell	
	<code>table-caption</code>	Element < TableTittle	
	<code>colspan</code> <code>rowspan</code>	Straddling in FrameMaker core	The New element needs to be added in EDD.
	<code>border</code>	FM core supports border in Table and Table cell.	The New element needs to be added in EDD.
	<code>background</code>	FM core supports background in Table and Table cell.	The New element needs to be added in EDD.

CSS property	CSS Property Values	Mapped to EDD property	Comments/Values
	table-column table-column-group		Not supported. Column selectors are also not supported as they are applied in table-column and table-column-group only.
caption-side	top bottom left right		Not supported
empty-cells	show hide		Not supported
table-layout	auto fixed		Not supported

CSS Selectors

The CSS selectors are mapped as in the following table:

CSS selector	Matches	EDD selector
*	any element	The * selector matches any single element of the document tree. So, properties specified using * are applied to all elements in EDD.
E	Any element Elem	Element(Container): E
F E	Any element E that is descendent of element F	If context is: * < F
F > E	Any E element that is child of F	Element (Container): E If context is: F
F + E	Any E element that immediately follows F	{after F} * + E maps to {notfirst}.
.class	any element with class "class"	Not supported
#id	element with ID id	Element (Container): E If context is: [IDname="id"]
:first-child	Any element that is the first child of its parent	{first}
:link :visited	Hyperlink visited or not	Ignored as it does not apply to FrameMaker.

CSS selector	Matches	EDD selector
:active :hover :focus	Any element that is activated by the user using the mouse, etc.	Ignored as it is for an interactive browser
:lang(<i>c</i>)	Any element whose content is in the ' <i>c</i> ' language	Element (Container):E General Rule: <ANY> If context is: [xml:lang=" <i>c</i> "]
[<i>att</i>]	Any element with attribute <i>att</i>	Not supported
[<i>att</i> = <i>val</i>]	Any element with attribute <i>att</i> and value <i>val</i> .	Element (Container):E General Rule: <ANY> If context is: [att=" <i>val</i> "]
[<i>att</i> ~= <i>val</i>]	Any element that includes the word " <i>val</i> " in its value.	Not supported
[<i>att</i> = " <i>val</i> "]	Any element with an <i>att</i> attribute value " <i>val</i> .."	Not supported
<i>E</i> :first-letter	The first letter of any element <i>E</i>	Not supported
<i>E</i> :first-line	The first line of any element <i>E</i>	Not supported
<i>E</i> :before <i>E</i> :after	The text to be inserted at the start/end of any element <i>E</i>	Maps to Prefix and Suffix rules in EDD. For more details, see the "content" property.

6

XML Schema to DTD Mapping

When XML documents are associated with an XML Schema declaration, FrameMaker can convert the Schema to a DTD declaration, from which you can create or modify an EDD. The content models of Schema and DTD are not identical. This chapter shows how Schema definitions are mapped into DTD definitions.

For details of how special objects are handled when converting Schema to DTD, see the individual object discussions in [Developer Guide, Part IV, Translating Between Markup Data and FrameMaker](#)

Note: The DTD generated from Schema always uses UTF8 encoding, regardless of the encoding used in the Schema file.

If you wish to modify the DTD that is generated automatically, you can do so. If you do this, reference the modified DTD from the original XML document. When FrameMaker imports an XML document that references both a Schema and DTD, it uses the DTD to create the FrameMaker elements, although it still validates the contents against the Schema.

Schema location

You can import an XML document that references a Schema file, and you can specify a Schema file in your structure application, to use for validating a document upon export to XML.

To specify a Schema file for use in exporting to XML, modify the `structapps.fm` file. The element `Schema`, a child of the `XmlApplication` element, specifies the Schema file path for export. The property `Namespace` in `XmlApplication` must be set to true if instance documents use namespaces. See [“Specifying a Schema for XML” on page 23](#)

For importing an XML document, include the path of the Schema file in the XML using attributes—`noNamespaceSchemaLocation` or `schemaLocation` depending on whether your schema includes a target namespace or not. A DTD is generated automatically when you import the XML, and the EDD is generated from the DTD.

Schema allows an XML document to reference multiple Schema locations in different namespaces using the root-element attribute `xsi:schemaLocation`, which can have multiple values. This feature has no equivalent in DTD. If an XML document references multiple Schema locations, FrameMaker uses only the first one for generating a DTD and for validation.

You can load XML documents that use `noNamespaceSchemaLocation`. For example:

```
<RootElementName id="RootElementID"
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
xsi:noNamespaceSchemaLocation="MySchema.xsd">
```

If an imported document references both a valid DTD location and a Schema location, the document is validated against the Schema. If there is no Schema location value, it is validated against the DTD. If neither location is specified, the load shows a warning similar to the one for a document that has no `DOCTYPE` statement.

If an imported document references both a DTD location and a Schema location, but the referenced DTD location is not valid, the load fails with the error “invalid external entity.” FrameMaker does not, in this case, generate a new DTD from the referenced Schema.

Namespace and Schema location attributes

The root element is not created automatically, therefore, the conversion process adds attributes for namespace definitions and schema location in all global elements specified in the Schema, which are then copied into the EDD that is created from the DTD. If you do add a root element, as recommended, these attributes are not needed, although they are not harmful.

If you wish, you can remove these extra attributes in two ways:

- After you generate an EDD from Schema, remove the extra attributes from the non-root elements in the EDD, and create a template. In this case, you do not need to provide an external DTD in the instance XML document.
- Remove the extra attributes from the non-root elements in the generated DTD, and save the modified DTD as an external DTD in the instance document. This is the technique to use if you want to modify the default mapping to DTD. In this case, you do not need a template. If you do wish to create a template, you can remove the attributes from the EDD as well.

Simple type mapping

All simple types in Schema translate to `#PCDATA` in DTD, and the Schema type `anyType` translates to the DTD type `ANY`. For example:

Schema

```
<xsd:element name="AString" type="xsd:string"/>
<xsd:element name="AnUnsignedInt" type="xsd:unsignedInt"/>
<xsd:element name="ABoolean" type="xsd:boolean"/>
<xsd:element name="AgYearMonth" type="xsd:gYearMonth"/>
<xsd:element name="AgMonthDay" type="xsd:gMonthDay"/>
<xsd:element name="AnyTypeElem" type="xsd:anyType"/>
```


DTD

```

<!ELEMENT AString(#PCDATA)>
<!ELEMENT AnUnsignedInt(#PCDATA)>
<!ELEMENT ABoolean (#PCDATA)>
<!ELEMENT AgYearMonth (#PCDATA)>
<!ELEMENT AgMonthDay (#PCDATA)>
<!ELEMENT AnyTypeElem (ANY)>

```

Attributes of simple type elements

Attribute of simple types translate to CDATA, NMTOKEN, NMTOKENS, ID, IDREFS, ENTITY, and so on. Enumeration facets in attributes are exported to DTD. Other simple type facets, `xsd:list` facets, and `xsd:union` facets are dropped.

Note the translation of `use`, `fixed` and `default` attribute combinations in the following example:

Schema

```

<xsd:attribute name="ReqdAttr" type="xsd:int" use="required"/>
<xsd:attribute name="OptAttr" type="xsd:int" use="optional"/>
<xsd:attribute name="ProhAttr" type="xsd:int" use="prohibited"/>
<xsd:attribute name="FixedReqdAttr" type="xsd:int" use="required"
  fixed="23"/>
<xsd:attribute name="OptDefAttr" type="xsd:int" use="optional"
  default="12"/>
<xsd:attribute name="FixedOptAttr" type="xsd:int" use="optional"
  fixed="25"/>
<xsd:attribute name="EnumAttr" use="optional" default="Male">
  <xsd:simpleType><xsd:restriction base="xsd:string">
    <xsd:enumeration value="Male"/>
    <xsd:enumeration value="Female"/>
  </xsd:restriction></xsd:simpleType>
</xsd:attribute>

```

DTD

```

<!ATTLIST ElemName
  FixedOptAttr NMTOKEN #FIXED "25"
  EnumAttr (Male|Female) "Male"
  OptDefAttr NMTOKEN "12"
  ReqdAttr NMTOKEN #REQUIRED
  FixedReqdAttr NMTOKEN #FIXED "23"
  OptAttr NMTOKEN #IMPLIED>

```

Complex type mapping

Complex content models in Schema translate to similar constructs in DTD, insofar as possible. If there are any errors in the Schema that result in a content model ambiguity, the content model is translated to ANY in DTD.

Group

The `group` content model in Schema translates to a group in DTD. For example:

Schema

```
<xsd:element name="GroupElem">
  <xsd:complexType><xsd:sequence><xsd:choice>
    <xsd:group ref="IntStr"/>
    <xsd:element name="MMIncl" type="xsd:string"/>
  </xsd:choice></xsd:sequence></xsd:complexType>
</xsd:element>

<xsd:group name="IntStr" id="Group1">
  <xsd:sequence>
    <xsd:element name="Int" type="xsd:int" minOccurs="2"
      maxOccurs="2"/>
    <xsd:element name="Str" type="xsd:string"/>
  </xsd:sequence>
</xsd:group>
```

DTD

```
<!ELEMENT GroupElem (((abc:Int,abc:Int),abc:Str)|abc:MMIncl)>
```

Sequence

A Schema `sequence` content model translates to a sequence in DTD. Note the translation of `minOccurs` and `maxOccurs` attribute value combinations in the following example.

Schema

```

<xsd:element name="TestOccurence">
  <xsd:complexType>
    <xsd:sequence>
      <xsd:element name="Min0" type="xsd:int" minOccurs="0"/>
      <xsd:element name="Max1" type="xsd:int" maxOccurs="1"/>
      <xsd:element name="Min0Max1" type="xsd:int" minOccurs="0"
        maxOccurs="1"/>
      <xsd:element name="Min1Max1" type="xsd:int" minOccurs="1"
        maxOccurs="1"/>
      <xsd:element name="Min2MaxI" type="xsd:int" minOccurs="2"
        maxOccurs="unbounded"/>
      <xsd:element name="Min0Max2" type="xsd:int" minOccurs="0"
        maxOccurs="2"/>
      <xsd:element name="Min2Max10" type="xsd:int" minOccurs="2"
        maxOccurs="10"/>
      <xsd:element name="Min2Max3" type="xsd:int" minOccurs="2"
        maxOccurs="3"/>
    </xsd:sequence>
  </xsd:complexType>

```

DTD

```

<!ELEMENT TestOccurence
  ((Min0?,Max1,Min0Max1?,Min1Max1,(Min2MaxI,Min2MaxI,Min2MaxI*),
  (Min0Max2*), (Min2Max10,Min2Max10,Min2Max10*),
  (Min2Max3, Min2Max3, Min2Max3?))>

```

Choice

A Schema choice content model translates to a choice in DTD. For example:

Schema

```

<xsd:element name="ChoiceElem">
  <xsd:complexType>
    <xsd:sequence>
      <xsd:choice>
        <xsd:element name="Int" type="xsd:int"/>
        <xsd:element name="Str" type="xsd:string"/>
        <xsd:element name="MMIncl" type="xsd:int"/>
      </xsd:choice>
    </xsd:sequence>
  </xsd:complexType>
</xsd:element>

```

DTD

```

<!ELEMENT ChoiceElem ((Int|Str)|MMIncl)>
<!ELEMENT Int          (#PCDATA)>
<!ELEMENT Str          (#PCDATA)>
<!ELEMENT MMIncl      (#PCDATA)>

```

All

A Schema `all` content model translates to a choice of elements with multiple occurrences in DTD. For example:

Schema

```

<xsd:element name="DataType">
  <xsd:complexType>
    <xsd:all>
      <xsd:element name="AName" type="xsd:Name"/>
      <xsd:element name="A QName" type="xsd:QName"/>
      <xsd:element name="AN CName" type="xsd:NCName"/>
      <xsd:element name="AnyURI" type="xsd:anyURI"/>
      <xsd:element name="ALanguage" type="xsd:language"/>
      <xsd:element name="AnID" type="xsd:ID"/>
      <xsd:element name="AnIDRef" type="xsd:IDREF"/>
      <xsd:element name="AIDREFS" type="xsd:IDREFS"/>
    </xsd:all></xsd:complexType></xsd:element>

```

DTD

```

<!ELEMENT DataType
  (AName | A QName | AN CName | AnyURI | ALanguage | AnID | AnIDRef | AIDREFS)*>

```

Named complex types

Named complex types in Schema are dropped, and their content model is substituted into the corresponding DTD elements. For example:

Schema

```

<xsd:element name="AddressDetails">
  <xsd:complexType><xsd:sequence>
    <xsd:element name="ToAddress" type="USAddress"/>
    <xsd:element name="FromAddress" type="USAddress"/>
  </xsd:sequence></xsd:complexType>
</xsd:element>

<xsd:complexType name="USAddress">
  <xsd:sequence>
    <xsd:element name="name" type="xsd:string"/>
    <xsd:element name="street" type="xsd:string"/>
    <xsd:element name="city" type="xsd:string"/>
    <xsd:element name="state" type="xsd:string"/>
    <xsd:element name="zip" type="xsd:int"/>
  </xsd:sequence>
  <xsd:attribute name="country" type="xsd:NMTOKEN" fixed="US"/>
  <xsd:attribute name="headquarter" type="xsd:string"
    use="required"/>
</xsd:complexType>

```

DTD

```

<!ELEMENT AddressDetails (ToAddress,FromAddress)>
<!ELEMENT ToAddress ((name,street,city,state),zip)>
<!ATTLIST ToAddress country NMTOKEN #FIXED "US"
          headquarter CDATA #REQUIRED >
<!ELEMENT FromAddress
          ((name,street,city,state),zip)>
<!ATTLIST FromAddress
          country NMTOKEN #FIXED "US"
          headquarter CDATA #REQUIRED >

<!ELEMENT name (#PCDATA)>
<!ELEMENT street (#PCDATA)>
<!ELEMENT city (#PCDATA)>
<!ELEMENT state (#PCDATA)>
<!ELEMENT zip (#PCDATA)>

```

Named attribute groups

Named attribute groups in Schema are dropped, and the attributes are put into the corresponding DTD attribute list. For example:

Schema

```
<xsd:element name="PersonalDetails">
  <xsd:complexType>
    <xsd:sequence>
      <xsd:element name="Name" type="xsd:string"/>
    </xsd:sequence>
    <xsd:attributeGroup ref="PersonalData"/>
  </xsd:complexType>
</xsd:element>

<xsd:attributeGroup name="PersonalData">
  <xsd:attribute name="Age" type="xsd:int" use="required"/>
  <xsd:attribute name="Gender">
    <xsd:simpleType><xsd:restriction base="xsd:string">
      <xsd:enumeration value="Male"/>
      <xsd:enumeration value="Female"/>
    </xsd:restriction></xsd:simpleType>
  </xsd:attribute>
</xsd:attributeGroup>
```

DTD

```
<!ELEMENT PersonalDetails (Name)>
<!ATTLIST PersonalDetails
           Age      NMTOKEN      #REQUIRED
           Gender   (Male|Female) #IMPLIED>
<!ELEMENT Name (#PCDATA)>
```

Abstract elements

For an abstract element in Schema is substituted into DTD elements using its own substitution group, if one is defined. Otherwise, the element maps directly to a DTD element. For example:

Schema

```

<xsd:element name="RootElement">
  <xsd:complexType><xsd:all>
    <xsd:element name="Elem1" type="xsd:int" minOccurs="0"/>
    <xsd:element ref="AbstractElem"/>
  </xsd:all></xsd:complexType>
</xsd:element>

<xsd:element name="AbstractElem" type="xsd:string"
  abstract="true"/>
<xsd:element name="Substitute1" type="xsd:string"
  substitutionGroup="AbstractElem"/>
<xsd:element name="Substitute2" type="xsd:string"
  substitutionGroup="AbstractElem"/>

```

DTD

```

<!ELEMENT RootElem (Elem1?|(Substitute1|Substitute2))*>
<!ELEMENT Elem1 (#PCDATA)>
<!ELEMENT Substitute1 (#PCDATA)>
<!ELEMENT Substitute2 (#PCDATA)>

```

Mixed content models

A mixed content model translates to a multiple occurrence of choice between elements in the content model and #PCDATA. Occurrence constraints associated with the elements and content model are ignored. For example:

Schema

```

<xsd:element name="RootElement">
  <xsd:complexType mixed="true"><xsd:sequence>
    <xsd:element name="elem1" type="xsd:string"
      minOccurs="0" maxOccurs="unbounded"/>
    <xsd:element name="elem2" type="xsd:positiveInteger"/>
    <xsd:element name="elem3" type="xsd:string"/>
    <xsd:element name="elem4" type="xsd:date" minOccurs="0"/>
  </xsd:sequence></xsd:complexType>
</xsd:element>

```

DTD

```

<!ELEMENT RootElem (#PCDATA|elem1|elem2|elem3|elem4)*>
<!ELEMENT elem1 (#PCDATA)>
<!ELEMENT elem2 (#PCDATA)>
<!ELEMENT elem3 (#PCDATA)>
<!ELEMENT elem4 (#PCDATA)>

```

Supported Schema features

Supported element qualification features of Schema are listed below with their mapping into DTD.

Defaults

The Schema `attributeFormDefault` and `elementFormDefault` are honored wherever they occur. For example:

Schema

```
<xsd:schema xmlns:xsd="http://www.w3.org/2001/XMLSchema"
  targetNamespace="Schema-abstract-elements"
  xmlns:abc="Schema-abstract-elements"
  elementFormDefault="qualified">

  <xsd:element name="RootElem">
    <xsd:complexType><xsd:sequence>
      <xsd:element name="Elem1" type="xsd:int"/>
    </xsd:sequence></xsd:complexType>
  </xsd:element>
```

DTD

```
<!ELEMENT abc:RootElem (abc:Elem1)>
```

Any

Any content model containing the Schema `<any>` element translates to the DTD `ANY` content model, regardless of additional content. For example:

Schema

```
<xsd:element name="AnyElem">
  <xsd:complexType><xsd:sequence>
    <xsd:element name="Elem1" type="xsd:int"/>
    <xsd:any namespace="http://www.w3.org/1999/xhtml"
      minOccurs="1" maxOccurs="unbounded"
      processContents="skip"/>
  </xsd:sequence></xsd:complexType>
</xsd:element>
```

DTD

```
<!ELEMENT AnyElem ANY>
<!ELEMENT Elem1 (#PCDATA)>
```

Notice in this example that the `Elem1` element is translated independently, and is not part of `AnyElem` in the DTD.

Extension and restriction of complex types

Extension and restriction of a complex type in Schema translates directly to the DTD. For example:

Schema

```
<xsd:element name="ElemA" type="ComplexTypeB"/>
<xsd:complexType name="ComplexTypeA">
  <xsd:sequence>
    <xsd:element name="elem1" type="xsd:string" maxOccurs="3"/>
    <xsd:element name="elem2" type="xsd:string"/>
  </xsd:sequence>
  <xsd:attribute name="attr1" type="xsd:NMTOKEN"/>
  <xsd:attribute name="attr2" type="xsd:string" use="required"/>
</xsd:complexType>

<xsd:complexType name="ComplexTypeB">
  <xsd:complexContent>
    <xsd:extension base="ComplexTypeA">
      <xsd:attribute name="attr3" type="xsd:date"
use="required"/>
    </xsd:extension>
  </xsd:complexContent>
</xsd:complexType>
```

DTD

```
<!ELEMENT ElemA      ((elem1,elem1*),elem2)>
<!ATTLIST ElemA      attr1      NMTOKEN   #IMPLIED
                    attr2      CDATA      #REQUIRED
                    attr3      NMTOKEN   #REQUIRED >

<!ELEMENT elem1      (#PCDATA)>
<!ELEMENT elem2      (#PCDATA)>
```

Include, import, and redefine

The `include`, `import` and `redefine` constructs allow one Schema file to refer to other Schema files. In converting to DTD, information from such referenced Schema files is included, but all elements are output to a single DTD. For example, if a Schema file `a.xsd` with namespace `ns_a` imports another Schema, `b.xsd` with namespace `ns_b`, the resulting DTD contains elements from both `ns_a` and `ns_b` namespaces.

The following example shows three Schema files; the first, `example.xsd`, includes the file named `include.xsd`, and imports the file named `import.xsd`. When the file `example.xsd` is imported into FrameMaker, the resulting DTD includes definitions for all three files.

Schema

First file, example.xsd

```
<schema targetNamespace="Include-Import-Example"
  xmlns="http://www.w3.org/2001/XMLSchema"
  xmlns:a="Include-Import-Example"
  xmlns:b="Import-schema" elementFormDefault="qualified">
<include schemaLocation="./include.xsd"/>
<import namespace="Import-schema" schemaLocation="./import.xsd"/>
<element name="rootElem1">
  <complexType><sequence>
    <element name="elem1" type="a:complexTypeA"/>
    <element ref="b:importElem1"/>
    <element ref="a:includeElem3"/>
  </sequence>
</complexType>
</element>
</schema>
```

Second file, include.xsd

```
<schema targetNamespace="Include-Import-Example"
  xmlns="http://www.w3.org/2001/XMLSchema"
  xmlns:a="Include-Import-Example"
  elementFormDefault="qualified">
<complexType name="complexTypeA"><sequence>
  <element name="includeElem1" type="string"/>
  <element name="includeElem2" type="string"/>
</sequence></complexType>
<element name="includeElem3" type="int"/>
</schema>
```

Third file, import.xsd

```
<schema targetNamespace="Import-schema"
  xmlns="http://www.w3.org/2001/XMLSchema"
  xmlns:c="Import-schema" elementFormDefault="qualified">
<element name="importElem1" type="int"/>
<element name="importElem2" type="string"/>
</schema>
```

DTD

```
<?xml version="1.0" encoding="UTF-8"?>
<!ELEMENT c:importElem1 (#PCDATA)>
<!ELEMENT c:importElem2 (#PCDATA)>
<!ELEMENT includeElem1 (#PCDATA)>
<!ELEMENT includeElem2 (#PCDATA)>
<!ELEMENT includeElem3 (#PCDATA)>
<!ELEMENT rootElem1 ((elem1,c:importElem1),includeElem3)>
<!ELEMENT elem1 (includeElem1,includeElem2)>
```

Unsupported Schema features

Features of Schema listed below cannot be mapped into DTD, and are dropped:

- Abstract types
- key, keyref, and unique
- Annotations

7

The CALS/OASIS Table Model

The CALS or the related OASIS table model is a specific set of element and attribute declarations for defining tables, originally defined in “Markup Requirements and Generic Style Specification for Electronic Printed Output and Exchange of Text,” MIL-M-28001B. The OASIS table model is an XML expression of the exchange subset of the full CALS Table Model DTD. If your markup documents use these elements and attributes or some simple variations of them, FrameMaker can translate them to tables and table parts without the assistance of read/write rules. The CALS model can be interpreted in various ways. This chapter describes the CALS elements and attributes as they are interpreted by FrameMaker.

Some attributes are common to several elements in the description of the table. In these cases, attribute values are inherited in the element hierarchy. The values of attributes associated with `<colspec>` and `<spanspec>` elements act as though they were on the parent element for inheritance purposes. This is, if a `<tgroup>` element has two `<colspec>` child elements and a `<thead>` child element, the attributes of the `<colspec>` elements apply to the `<thead>` element unless that element has its own `<colspec>` elements with attribute values that override the inherited ones. If you want to change how FrameMaker processes any attribute of a `<colspec>` or `<spanspec>` element, you refer to the attribute as a formatting property.

In the CALS model, the `<table>` element has an `<orient>` attribute. This attribute is not supported in FrameMaker, because there is no way in a FrameMaker table to specify orientation on the page.

FrameMaker properties that DO NOT have corresponding CALS attributes

FrameMaker Property	For FrameMaker Elements of Type	Corresponding CALS Attribute
column widths	table (CALS: tgroup)	(none)

Column widths: Width of successive columns in the table. Each value is either an absolute width or a width proportional to the size of the entire table. If proportional widths are used, the CALS `-pgwide-` attribute determines the table width. For example, to specify that the first two columns are each one-quarter the size of the table, and the third column is half the size of the table, you could write a rule to specify your column widths as “25* 25* 50*”. Valid units and abbreviations for the “column width” formatting property are:

Unit	Abbreviation
centimeter	cm
cicero	cc
didot	dd
inch	in (in FrameMaker dialog boxes, " is also used, but not for "column width" formatting property)
millimeter	mm
pica	pc (or pi)
point	pt

FrameMaker Property	For FrameMaker Elements of Type	Corresponding CALS Attribute
maximum height	row	(none)
Maximum height of a row in a table.		
minimum height	row	(none)
Minimum height of a row in a table.		
row type	row	(none)
Whether the associated table row is a heading, footing, or body row, or the associated table cell occurs in a row of that type.		
horizontal straddle	cell	(none)
How many columns this straddle cell spans		
vertical straddle	cell	(none)
How many rows this straddled cell spans		

Element and attribute definition list declarations

The element and attribute declarations as used by FrameMaker are as follows:

```
<!ENTITY % yesorno "NUMBER">
```

```

<!ELEMENT table - - (title?, tgroup+)>
<!ATTLIST table
  colsep    %yesorno; #IMPLIED
  frame     (all|top|bottom|topbot|sides|none) #IMPLIED
  pgwide    %yesorno; #IMPLIED
  rowsep    %yesorno; #IMPLIED
  tabstyle  NMTOKEN    #IMPLIED
>

<!ELEMENT title - - (#PCDATA)>

<!ELEMENT tgroup - 0 (colspec*, spanspec*, thead?, tfoot?, tbody)>
<!ATTLIST tgroup
  align     (left|center|right|justify|char) #IMPLIED
  char      CDATA      #IMPLIED
  charoff   NUTOKEN    #IMPLIED
  colsep    %yesorno; #IMPLIED
  cols      NUMBER     #REQUIRED
  rowsep    %yesorno; #IMPLIED
  tgroupstyle NMTOKEN  #IMPLIED
>

<!ELEMENT colspec - 0 EMPTY>
<!ATTLIST colspec
  align     (left|center|right|justify|char) #IMPLIED
  char      CDATA      #IMPLIED
  charoff   NUTOKEN    #IMPLIED
  colname   NMTOKEN    #IMPLIED
  colnum    NUMBER     #IMPLIED
  colsep    %yesorno; #IMPLIED
  colwidth  CDATA      #IMPLIED
  rowsep    %yesorno; #IMPLIED
>

<!ELEMENT spanspec - 0 EMPTY>
<!ATTLIST spanspec
  align     (left|center|right|justify|char) #IMPLIED
  char      CDATA      #IMPLIED
  charoff   NUTOKEN    #IMPLIED
  colsep    %yesorno; #IMPLIED
  nameend   NMTOKEN    #REQUIRED
  namest    NMTOKEN    #REQUIRED
  rowsep    %yesorno; #IMPLIED
  spanname  NMTOKEN    #REQUIRED
>

```

```

<!ELEMENT thead - O (colspec*, row+)>
<!ATTLIST thead
  valign (top|middle|bottom) "bottom"
>

<!ELEMENT tfoot - O (colspec*, row+)>
<!ATTLIST tfoot
  valign (top|middle|bottom) "top"
>

<!ELEMENT tbody - O (row+)>
<!ATTLIST tbody
  valign (top|middle|bottom) "top"
>

<!ELEMENT row - O (entry+)>
<!ATTLIST row
  rowsep %yesorno;          #IMPLIED
  valign (top|middle|bottom) "top"
>

<!ELEMENT entry - O (#PCDATA)>
<!ATTLIST entry
  align    (left|center|right|justify|char) #IMPLIED
  char     CDATA          #IMPLIED
  charoff  NUTOKEN        #IMPLIED
  colname  NMTOKEN        #IMPLIED
  colsep   %yesorno;     #IMPLIED
  morerows NUMBER         #IMPLIED
  nameend  NMTOKEN        #IMPLIED
  namest   NMTOKEN        #IMPLIED
  rotate   %yesorno;     #IMPLIED
  rowsep   %yesorno;     #IMPLIED
  spanname NMTOKEN        #IMPLIED
  valign   (top|middle|bottom) #IMPLIED
>

```

Element structure

A CALS table has an optional title followed by one or more `tgroup` elements. This allows, for example, different portions of one table to have different numbers of columns. In practice, most CALS tables have a single `tgroup` element. The `tgroup` element is the major portion of the table. It has several optional parts: multiple `colspec` and `spanspec` elements followed by (at most) one heading and one footing element. The only required sub-element of a `tgroup` element is its body. Unlike the FrameMaker model of table structure, the CALS model has its `tgroup` element appearing after the footing element.

The `colspec` empty element has attributes describing characteristics of a table column. The `spanspec` empty element has attributes describing straddling characteristics of a portion of a table. These elements have no counterpart in FrameMaker. They exist only to have their attribute values specify information about other elements in the table.

The `thead` and `tfoot` heading and footing elements contain their own optional `colspec` elements followed by one or more rows.

The `tbody` element contains one or more rows.

As supported by FrameMaker, a table row consists of a set of cells in `entry` elements, each of which can contain only text. Readers familiar with the CALS model may notice that these declarations do not include the `entrytbl` element which supports creating tables within tables. FrameMaker does not allow tables within tables, so does not support this element.

Attribute structure

Elements in the CALS table model use attributes to describe properties of the table such as cell alignment or straddling behavior. For information on the meaning of the CALS attributes, see [“Formatting properties for tables” on page 343](#).

Inheriting attribute values

Some attributes are common to several elements in the description of a table. In these cases, attribute values are inherited in the element hierarchy. The values of attributes associated with `colspec` and `spanspec` elements act as though they were on the parent element for inheritance purposes. That is, if a `tgroup` element has two `colspec` child elements and a `thead` child element, the attributes of the `colspec` elements apply to the `thead` element unless that element has its own `colspec` elements with attribute values that override the inherited ones.

Orient attribute

In the CALS model, the `table` element has an `orient` attribute. This attribute is not supported in FrameMaker, because there is no way in a FrameMaker table to specify orientation on the page.

Straddling attributes

A `spanspec` element describes a column range so that a straddle cell can describe which columns it spans by referencing a `spanspec` through its `spanname` attribute.

An `entry` element specifies which columns it occupies by one of three methods:

- Using the `namest` and `nameend` attributes to reference columns explicitly. The `namest` attribute indicates the first column in the straddle; the `nameend` attribute indicates the last column.

- Using the `spanname` attribute as an indirect reference to the columns.
- Using the `colname` attribute (for a non-straddled cell).

8

Read/Write Rules for the CALS/OASIS Table Model

By default, FrameMaker can read and write CALS (or OASIS) tables without your intervention. For information on what it does by default and how you can change that behavior with read/write rules, see [Chapter 22, "Translating Tables."](#) FrameMaker does not use read/write rules to implement its default interpretation of CALS tables. However, to help your understanding of the default interpretation, this chapter contains a set of rules that encapsulate the software's default behavior for CALS tables.

As described in [Chapter 22, "Translating Tables,"](#) the software's default behavior is different depending on whether the `table` element is a container element or a table element in FrameMaker. The only difference is what type of element `table` becomes and what happens to the `tgroup` element. All other elements and attributes always translate in the same way.

```
element "table" {
  /* If table is a container element, use this subrule: */
  is fm element;

  /* If table is a table element, use this subrule: */
  is fm table element;

  /* The rest of the subrules for table are always applicable. */
  attribute "tabstyle" is fm property table format;
  attribute "tocentry" is fm attribute;
  attribute "frame"
  {
    is fm property table border ruling;
    value "top"      is fm property value top;
    value "bottom"  is fm property value bottom;
    value "topbot"  is fm property value top and bottom;
    value "all"     is fm property value all;
    value "sides"   is fm property value sides;
    value "none"    is fm property value none;
  }
  attribute "colsep" is fm property column ruling;
  attribute "rowsep" is fm property row ruling;
  attribute "orient" is fm attribute;
  attribute "pgwide" is fm property page wide;
}
element "tgroup"
{
```

```

/* If table is a container element, use this subrule: */
is fm table element;

/* If table is a table element, use this subrule: */
unwrap;

/*The rest of the subrules for tgroup are always applicable.*/
attribute "cols"          is fm property columns;
attribute "tgroupstyle" is fm property table format;
attribute "colsep"        is fm property column ruling;
attribute "rowsep"        is fm property row ruling;
attribute "align"         is fm attribute;
attribute "charoff"       is fm attribute;
attribute "char"          is fm attribute;
}

element "colspec"
{
  is fm colspec;
  attribute "colnum"      is fm property column number;
  attribute "colname"     is fm property column name;
  attribute "align"       is fm property cell alignment type;
  attribute "charoff"     is fm property cell alignment offset;
  attribute "char"        is fm property cell alignment character;
  attribute "colwidth"   is fm property column width;
  attribute "colsep"      is fm property column ruling;
  attribute "rowsep"      is fm property row ruling;
}

element "spanspec"
{
  is fm spanspec;
  attribute "spanname"    is fm property span name;
  attribute "namestart"   is fm property start column name;
  attribute "nameend"     is fm property end column name;
  attribute "align"       is fm property cell alignment type;
  attribute "charoff"     is fm property cell alignment offset;
  attribute "char"        is fm property cell alignment character;
  attribute "colsep"      is fm property column ruling;
  attribute "rowsep"      is fm property row ruling;
}

element "thead"
{
  is fm table heading element;
  attribute "valign" is fm attribute;
}

```

```
element "tfoot"
{
    is fm table footing element;
    attribute "valign" is fm attribute;
}

element "tbody"
{
    is fm table body element;
    attribute "valign" is fm attribute;
}

element "row"
{
    is fm table row element;
    attribute "valign" is fm attribute;
    attribute "rowsep" is fm property row ruling;
}

element "entry"
{
    is fm table cell element;
    attribute "colname" is fm property column name;
    attribute "namest" is fm property start column name;
    attribute "nameend" is fm property end column name;
    attribute "spanname" is fm property span name;
    attribute "morerows" is fm property more rows;
    attribute "colsep" is fm property column ruling;
    attribute "rowsep" is fm property row ruling;
    attribute "rotate" is fm property rotate;
    attribute "valign" is fm attribute;
    attribute "align" is fm attribute;
    attribute "charoff" is fm attribute;
    attribute "char" is fm attribute;
}
```


9

SGML Declaration

To be complete, an SGML document must start with an SGML declaration. This chapter contains the text of the SGML declaration used by FrameMaker when you do not supply one. It also describes the variants of the concrete syntax that you can use in your SGML declaration and unsupported optional SGML features.

Note: XML: The XML specification states that XML must use a specific SGML declaration. This chapter pertains only to SGML structure applications. If you are only working with XML markup, you may skip this chapter.

When you import an SGML document, FrameMaker first searches for the declaration in the SGML document. If the software does not find the declaration there, it looks for an SGML declaration specified by your SGML application definition. If your definition does not specify an SGML declaration, then the software uses the declaration described below.

When you export a FrameMaker document to SGML, FrameMaker first tries to use an SGML declaration you specified by your application. If you haven't specified one, it uses the SGML declaration described below.

For information on how to specify an SGML declaration as part of an application, see [Developer Guide, page 133: Application definition file](#).

Text of the default SGML declaration

The SGML declaration provided by FrameMaker uses ISO Latin-1 as the character set, the reference concrete syntax, and the reference capacity set. The declaration enables the optional features OMITTAG, SHORTTAG, and FORMAL.

For information on the default translation between the FrameMaker and ISO Latin-1 character sets, see [Chapter 11, "Character Set Mapping."](#) For information on using other ISO character sets, see [Chapter 10, "ISO Public Entities."](#)

The text of the default SGML declaration is as follows:

```
<!SGML "ISO 8879:1986"  
CHARSET  
    BASESET "ISO Registration Number 100//CHARSET ECMA-94 Right  
Part of Latin Alphabet Nr. 1//ESC 2/13 4/1"
```

```
DESCSET
  0 9 UNUSED
  9 2 9
 11 2 UNUSED
 13 1 13
 14 18 UNUSED
 32 95 32
 127 1 UNUSED
 128 127 128
 255 1 UNUSED

CAPACITY
  PUBLIC "ISO 8879:1986//CAPACITY Reference//EN"

SCOPE DOCUMENT

SYNTAX

  SHUNCHAR          0 1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18
19 20
                    21 22 23 24 25 26 27 28 29 30 31 127 255

  BASESET "ISO Registration Number 100//CHARSET ECMA-94 Right
Part of Latin Alphabet Nr. 1//ESC 2/13 4/1"

  DESCSET 0 256 0

  FUNCTION RE 13
    RS 10
    SPACE 32
    TAB SEPCHAR 9

  NAMING          LCNMSTRT ""
    UCNMSTRT ""
    LCNMCHAR "&#45;&#46;"
    UCNMCHAR "&#45;&#46;"
    NAMECASE
      GENERAL YES
      ENTITY NO

  DELIM          GENERAL SGMLREF
    SHORTREF SGMLREF

  NAMES SGMLREF

  QUANTITY SGMLREF

FEATURES
```



```
MINIMIZE DATATAG NO
           OMITTAG YES
           RANK NO
           SHORTTAG YES

LINK      SIMPLE NO
           IMPLICIT NO
           EXPLICIT NO

OTHER CONCUR NO
        SUBDOC NO
        FORMAL YES

APPINFO NONE

>
```

SGML concrete syntax variants

The SGML parser used by FrameMaker allows these modifications to the SGML reference concrete syntax:

- The NAMECASE parameter of the SGML declaration can be changed. The default settings below specify that general names are *not* case sensitive (YES), and entity names *are* case sensitive (NO):

```
NAMECASE
           GENERAL YES
           ENTITY NO
```

- Reserved names can be changed.
- Short references can, but need not, be used. If they are used, the only possible short reference delimiter set is that of the reference concrete syntax.
- The value for the NAMELEN quantity can be increased up to 239.
- The values for the following quantities can be increased, but not to more than 30 times their value in the reference concrete syntax:

```
ATTCNT
ATTSPLEN
BSEQLEN
ENTLVL
LITLEN
PILEN
TAGLEN
TAGLVL
```

- The following quantities can be increased up to 253:

GRPCNT
GRPGTCNT
GRPLVL

No SGML read/write rules are needed to provide for variant concrete syntaxes. FrameMaker obtains the information from the SGML declaration.

The concrete syntax declared in the SGML declaration must be used for the entire document; if a variant concrete syntax is declared, the reference concrete syntax cannot be used in the prolog. Thus, the concrete syntax scope parameter must be:

SCOPE DOCUMENT

Unsupported optional SGML features

The SGML standard defines some features as optional, meaning that a specific implementation does not have to accommodate these features to be considered a conforming SGML system.

The following optional SGML features are not supported by FrameMaker:

- DATATAG
- RANK
- LINK
- SUBDOC
- CONCUR

Your DTD and SGML documents cannot use any of these features. If they do, the FrameMaker signals an error and terminates processing. You cannot change this behavior by providing an SGML API client.

10

ISO Public Entities

Annex D of the SGML standard defines several sets of internal `SDATA` entities. Each entity represents a character; each entity set is a logical grouping of these entities. DTDs frequently include these entity sets by using parameter entity references to external entities accessed with a public identifier. People in the SGML community frequently interchange DTDs and SGML documents with such entity references and assume that the recipient can interpret the public identifiers. FrameMaker includes copies of these entity sets and makes them available using the default handling of public identifiers.

Note: XML: The XML specification does not allow `SDATA` entities, but it does allow UNICODE and predefined character entities for special characters. This chapter pertains only to SGML structure applications. If you are only working with XML markup, you may skip this chapter.

These entity sets are defined in an ISO standard and are accessed with public identifiers, so they are commonly known as *ISO public entity sets*. The public entity sets fall into the following categories:

Entity set	Description
Latin alphabetic characters	Latin alphabetic characters used in Western European languages
Greek alphabetic characters	Letters of the Greek alphabet
Greek symbols	Greek character names for use as variable names in technical applications
Cyrillic alphabetic characters	Cyrillic characters used in the Russian language
Numeric and special graphic characters	Minimum data characters and reference concrete syntax characters
Diacritical mark characters	Diacritical marks
Publishing characters	Well-known publishing characters
Technical symbols	Technical symbols
Added math symbols	Mathematical symbols

If your application uses FrameMaker's support of ISO entity sets, you may want to create palettes your end user can use to enter these entities in a FrameMaker document. For information on creating these palettes, see [Developer Guide, page 334: Facilitating entry of special characters that translate as entities](#).

What you need to use ISO public entities

For your end users to use characters from the ISO public entity sets, your application needs two pieces of information for each character entity: the entity's declaration, and an SGML read/write rule that tells FrameMaker how to translate a reference to that entity in an SGML document to a character or variable in a FrameMaker document. FrameMaker provides this information in two files for each entity set.

All files used for ISO public entity sets are in the directory `$STRUCTDIR/isoents`. For information on the location of this directory on your system, see [Developer Guide, page 131: Location of structure files](#). The files for each entity set are as follows:

Entity set	Entity declaration files	Read/write rules files
Latin alphabetic characters	<code>isolat1.ent</code>	<code>isolat1.rw</code>
	<code>isolat2.ent</code>	<code>isolat2.rw</code>
Greek alphabetic characters	<code>isogrkl.ent</code>	<code>isogrkl.rw</code>
	<code>isogrkl2.ent</code>	<code>isogrkl2.rw</code>
Greek symbols	<code>isogrkl3.ent</code>	<code>isogrkl3.rw</code>
	<code>isogrkl4.ent</code>	<code>isogrkl4.rw</code>
Cyrillic alphabetic characters	<code>isocyr1.ent</code>	<code>isocyr1.rw</code>
	<code>isocyr2.ent</code>	<code>isocyr2.rw</code>
Numeric and special graphic characters	<code>isonum.ent</code>	<code>isonum.rw</code>
Diacritical mark characters	<code>isodia.ent</code>	<code>isodia.rw</code>
Publishing characters	<code>isopub.ent</code>	<code>isopub.rw</code>
Technical symbols	<code>isobox.ent</code>	<code>isobox.rw</code>
	<code>isotech.ent</code>	<code>isotech.rw</code>
Added math symbols	<code>isoamso.ent</code>	<code>isoamso.rw</code>
	<code>isoamsb.ent</code>	<code>isoamsb.rw</code>
	<code>isoamsr.ent</code>	<code>isoamsr.rw</code>
	<code>isoamsn.ent</code>	<code>isoamsn.rw</code>
	<code>isoamsa.ent</code>	<code>isoamsa.rw</code>
	<code>isoamsc.ent</code>	<code>isoamsc.rw</code>

Entity declaration files

Each entity declaration file starts with two comment declarations that suggest both the public identifier and the entity name by which to identify the entity set. For the ISO Latin-1 entity set, these comments are:

```
<!-- (C) International Organization for Standardization 1986
      Permission to copy in any form is granted for use with
      conforming SGML systems and applications as defined in
      ISO 8879, provided this notice is included in all copies.
-->
<!-- Character entity set. Typical invocation:
      <!ENTITY % ISOLat1 PUBLIC
           "ISO 8879-1986//ENTITIES Added Latin 1//EN">
      %ISOLat1;
-->
```

After the initial comments, an entity declaration file consists of a sequence of entity declarations. For example, the first few entity declarations for ISO Latin-1 are as follows:

```
<!ENTITY aacute SDATA "[aacute]"---=small a, acute accent-->
<!ENTITY Aacute SDATA "[Aacute]"---=capital A, acute accent-->
<!ENTITY acirc SDATA "[acirc ]"---=small a, circumflex accent-->
<!ENTITY Acirc SDATA "[Acirc ]"---=capital A, circumflex accent-->
<!ENTITY agrave SDATA "[agrave]"---=small a, grave accent-->
<!ENTITY Agrave SDATA "[Agrave]"---=capital A, grave accent-->
<!ENTITY aring SDATA "[aring ]"---=small a, ring-->
<!ENTITY Aring SDATA "[Aring ]"---=capital A, ring-->
```

You should never modify these files, because they provide the standard ISO public entity declarations.

If your SGML documents use the standard invocations for ISO public entity sets, you do not have to provide any information in your application definition on where to find these entities; FrameMaker finds them in the default directory. If necessary, you can provide explicit `public` statements to substitute alternative versions of the entity sets. For information on working with application definitions, see [Developer Guide, page 133: Application definition file](#).

Entity read/write rules files

FrameMaker provides read/write rules for many of the entities in the ISO public entity sets. The rules are organized in files for each public entity set. These files are not complete rules documents. Instead, they are simply lists of rules or comments explaining which entities do not have default correspondences.

You can include individual files in your application's read/write rules document by using the `#include` statement. To include the rules for all of the ISO public entity sets, use this single statement:

```
#include isoall.rw
```

To include only the ISO Latin-1 entity set, use these statements:

```
#include isolat1.rw
#include isolat2.rw
```

For more information on read/write rules files, see [Developer Guide, Chapter 18, Read/Write Rules and Their Syntax](#)

Format of entity rules

By default, FrameMaker has rules for each entity that can be represented in FrameMaker using the standard FrameMaker character set, the Symbol font, or the Zapf Dingbat font and for a few (such as the fractions in `isonum`) that can be represented with a FrameMaker user variable. Entities that cannot be represented in this way do not have a default translation. Users of your application may have more fonts available. If so, you can modify these rules files to include translations for other entities.

The default rules for entities available in the default character sets or through variables differ depending on how FrameMaker translates the entity.

- If the character appears in FrameMaker's standard character set and requires no special formatting, the rule has the following form:

```
entity "ename" is fm char code;
```

where *ename* is the entity name and *code* is the character code. For example, the following rule is for the small letter "a" with an acute accent:

```
entity "aacute" is fm char 0x87;
```

- If the character appears in FrameMaker's Symbol or Zapf Dingbat character set or appears in FrameMaker's standard character set, but requires special formatting, the rule has the following form:

```
entity "ename" is fm char code in "fntag";
```

where *ename* is the entity name, *code* is the character code, and *fntag* is one of the character tags defined below. For example, the following rule is for the plus-or-minus sign:

```
entity "plusnm" is fm char 0xb1 in "FmSymbol";
```

- If the character can be represented by an FrameMaker variable, the rule has the following form:

```
entity "ename" is fm variable "var";
```

where *ename* is the entity name and *var* is one of the FrameMaker variables defined below. For example, the following rule is for the fraction one-half:

```
entity "frac12" is fm variable "FmFrac12";
```

For details on how each entity translates into a FrameMaker document, see the individual rules files.

Character formats

As mentioned above, the rules for some character entities refer to FrameMaker character formats or variable names. FrameMaker has default definitions for these character formats:

Character format	Defined as
FmDenominator	Default font, subscripted; other characteristics As Is
FmDingbats	Zapf Dingbat font; other characteristics As Is
FmNumerator	Default font, superscripted; other characteristics As Is
FmSdata	Default font, underlined and in green; other characteristics As Is
FmSuperscript	Default font superscripted; other characteristics As Is
FmSymbol	Symbol font; other characteristics As Is
FmUnderlineSymbol	Symbol font, underlined; other characteristics As Is

Variables

FrameMaker also has default definitions for these variables:

Variable	Defined as
FmCare-of	‰
FmEmsp13	an em space
FmFrac12	$\frac{1}{2}$
FmFrac13	$\frac{1}{3}$
FmFrac14	$\frac{1}{4}$
FmFrac15	$\frac{1}{5}$
FmFrac16	$\frac{1}{6}$
FmFrac18	$\frac{1}{8}$
FmFrac23	$\frac{2}{3}$
FmFrac25	$\frac{2}{5}$
FmFrac34	$\frac{3}{4}$
FmFrac35	$\frac{3}{5}$
FmFrac38	$\frac{3}{8}$
FmFrac45	$\frac{4}{5}$
FmFrac56	$\frac{5}{6}$
FmFrac58	$\frac{5}{8}$
FmFrac78	$\frac{7}{8}$

Your end user's documents may not have these character formats or variables defined. When FrameMaker imports an SGML document with an entity reference that needs one of these formats or variables, it checks whether the template defined in the SGML application provides the definition. If so, it uses the information from the template. If not, it uses its own definitions, copying the definition to the appropriate catalog of the document being processed and using it to process the entity.

What happens with the declarations and rules

Your application may use some or all of the entity declarations and read/write rules provided with FrameMaker. In addition, you may choose to have different declarations or rules for some or all of the entities.

If you want to use the translations provided by FrameMaker with no changes, you do so in one of two ways.

- If your application has no other read/write rules, then you do not have to explicitly mention the rules for these entity sets. That is, if the definition of your application does not include a read/write rules file, FrameMaker behaves as though it had a rules file that included only the ISO public entity rules.
- On the other hand, if your application does have a read/write rules file, then that file must explicitly include the rules for the ISO public entity sets in which you're interested. If you want all of them, add the following line to your file:

```
#include isoall.rw
```

When you create a new read/write rules file, this line is automatically included.

If you want to use only the rules that FrameMaker provides, be sure that your rules file has no additional `entity` rules referring to these entities. However, you may want to have FrameMaker translate most but not all of these entities in the way it provides, while you change the behavior for some of them with rules or entity declarations. To do this, include an extra entity declaration or rule for the appropriate entities.

For example, assume the DTD for your application is called `myapp.dtd` and includes the following lines:

```
<!ENTITY % ISolat1 PUBLIC
    "ISO 8879-1986//ENTITIES Added Latin 1//EN">
%ISolat1;
```

Further, assume the application has no rules or has a rules document that contains the following lines:

```
#include "isolat1.rw"
#include "isolat2.rw"
```


The default version of `isolat1.rw` contains the rule:

```
entity "aacute" is fm char 0x87;
```

This translates references to the `aacute` entity as the small letter a with an acute accent. Suppose, however, that your application needs this entity, instead, to translate as a particular bitmap that you store as a reference element in the FrameMaker document template. You can accomplish this by adding either a new entity declaration or a new rule.

To continue the example, assume you import an SGML document that begins as follows:

```
<!DOCTYPE myapp SYSTEM "myapp.dtd" [  
  <!ENTITY aacute SDATA "fm ref: acute-a">  
>
```

This SGML document has two declarations for `aacute`. The parser uses the first one it encounters. Since the parser processes the external DTD subset after it processes the internal DTD subset, it finds the declaration that uses the reference element first and this is the entity declaration FrameMaker uses. Since FrameMaker recognizes the `fm ref` in the parameter literal, it uses that parameter literal to process the entity reference and ignores any rules that refer to the entity. The resulting document includes the reference element for the entity reference.

Instead of including the declaration for `aacute` that uses the `fm ref` parameter literal, you can add the following rule to your rules file:

```
entity "aacute" is fm reference element "acute-a";
```

This translates references to the `aacute` entity as the small letter a with an acute accent. Suppose, however, that your application needs this entity, instead, to translate as a particular bitmap that you store as a reference element in the FrameMaker document template. You accomplish this by adding a rule for that entity before the `#include` statements, as follows:

```
entity "aacute" is fm reference element "acute-a";
```

Remember that FrameMaker uses the first rule in a rules file that applies to a particular situation. Therefore, if you use this rule, then the line in the example that includes `isolat1.rw` must occur after this rule. That is, your rules file must look like:

```
entity "aacute" is fm reference element "acute-a";  
. . .  
#include isolat1.rw  
. . .
```

If, instead, it looks like:

```
#include isolat1.rw  
. . .  
entity "aacute" is fm reference element "acute-a";  
. . .
```

FrameMaker finds the rule in `isolat1.rw` before your rule and use that to process references to the `aacute` entity.

FrameMaker has rules for entities in the ISO public entity sets for which there is a direct correspondence in one of its standard character sets or which can be created using a character from those character sets. It does not provide rules for entities that would require a different character set or a graphic.

If you reference an ISO public entity for which there is not a rule, the software treats it as it does any other entity that does not have a corresponding rule. You can change this behavior with the `entity` rule. For more information on FrameMaker's translation of entities in the absence of rules and for information on how you can modify this, see [Developer Guide, Chapter 21, Translating Entities and Processing Instructions](#)

11

Character Set Mapping

FrameMaker writes SGML documents using the ISO Latin-1 character set. This character set differs from FrameMaker's character set. Consequently, the software uses a default character set mapping to translate between the character sets.

Note: XML: The XML specification allows UNICODE in content and in markup tokens, so the use of ISO character sets is not necessary. FrameMaker supports the full range of UNICODE in the content of an XML document, and offers limited support of characters in markup tokens. For more information, see [Developer Guide, page 101: Supported characters in element and attribute names](#).

If you are only working with XML markup, you may skip this chapter.

FrameMaker includes copies of other ISO public entity sets and provides rules to handle them for your application. For information on how FrameMaker supports ISO public entities, see [Chapter 10, "ISO Public Entities."](#)

This chapter describes the default mapping between the FrameMaker character set and the ISO Latin-1 character set. You can change this mapping by using the `character map` rule as described in ["character map" on page 47](#).

To determine the mapping for a particular character, use the table on the next page as follows:

- For a character in the ISO Latin-1 character set, find the hexadecimal character code for the character of interest in the leftmost column. Read the mapping in the column labelled "Mapping from ISO Latin-1 to FrameMaker." The entry on the left side of the equal sign is the ISO Latin-1 character code. The entry on the right side of the equal sign is the character's translation in FrameMaker. For example, the character code `\xA1` has the entry:

```
\xA1 = \xC1
```

This means that the ISO Latin-1 character `\xA1` translates to the FrameMaker character `\xC1`.

- For a character in the FrameMaker character set, find the hexadecimal character code for the character of interest in the leftmost column. Read the mapping in the column labelled "Mapping from FrameMaker to ISO Latin-1." The entry on the right side of the equal sign is the FrameMaker character code. The entry on the left side of the equal sign is the character's translation in ISO Latin-1. For example, the character code `\x10` has the entry:

```
\x20 = \x10
```

This means that the FrameMaker character `\x10` translates to the ISO Latin-1 character `\x20`.

- If there is no row corresponding to a character code, then that character code is the same in both character sets.

Character code	Mapping from ISO Latin-1 to FrameMaker	Mapping from FrameMaker to ISO Latin-1
\x00	\x00 = trap	trap = \x00
\x01	\x01 = trap	trap = \x01
\x02	\x02 = trap	trap = \x02
\x03	\x03 = trap	trap = \x03
\x04	\x04 = trap	trap = \x04
\x05	\x05 = trap	trap = \x05
\x06	\x06 = trap	trap = \x06
\x07	\x07 = trap	trap = \x07
\x08	\x08 = trap	\x09 = \x08
\x09	\x09 = \x08	\x0A = \x09
\x0A	\x0A = \x0A	\x0A = \x0A
\x0B	\x0B = trap	trap = \x0B
\x0C	\x0C = trap	trap = \x0C
\x0D	\x0D = trap	trap = \x0D
\x0E	\x0E = trap	trap = \x0E
\x0F	\x0F = trap	trap = \x0F
\x10	\x10 = trap	\x20 = \x10
\x11	\x11 = trap	\x20 = \x11
\x12	\x12 = trap	\x20 = \x12
\x13	\x13 = trap	\x20 = \x13
\x14	\x14 = trap	\x20 = \x14
\x15	\x15 = trap	\x2D = \x15
\x16	\x16 = trap	trap = \x16
\x17	\x17 = trap	trap = \x17
\x18	\x18 = trap	trap = \x18
\x19	\x19 = trap	trap = \x19
\x1A	\x1A = trap	trap = \x1A
\x1B	\x1B = trap	trap = \x1B
\x1C	\x1C = trap	trap = \x1C
\x1D	\x1D = trap	trap = \x1D
\x1E	\x1E = trap	trap = \x1E
\x1F	\x1F = trap	trap = \x1F

Character code	Mapping from ISO Latin-1 to FrameMaker	Mapping from FrameMaker to ISO Latin-1
\x7F	\x7F = trap	trap = \x7F
\x80	\x80 = trap	\xC4 = \x80
\x81	\x81 = trap	\xC5 = \x81
\x82	\x82 = trap	\xC7 = \x82
\x83	\x83 = trap	\xC9 = \x83
\x84	\x84 = trap	\xD1 = \x84
\x85	\x85 = trap	\xD6 = \x85
\x86	\x86 = trap	\xDC = \x86
\x87	\x87 = trap	\xE1 = \x87
\x88	\x88 = trap	\xE0 = \x88
\x89	\x89 = trap	\xE2 = \x89
\x8A	\x8A = trap	\xE4 = \x8A
\x8B	\x8B = trap	\xE3 = \x8B
\x8C	\x8C = trap	\xE5 = \x8C
\x8D	\x8D = trap	\xE7 = \x8D
\x8E	\x8E = trap	\xE9 = \x8E
\x8F	\x8F = trap	\xE8 = \x8F
\x90	\x90 = trap	\xEA = \x90
\x91	\x91 = trap	\xEB = \x91
\x92	\x92 = trap	\xED = \x92
\x93	\x93 = trap	\xEC = \x93
\x94	\x94 = trap	\xEE = \x94
\x95	\x95 = trap	\xEF = \x95
\x96	\x96 = trap	\xF1 = \x96
\x97	\x97 = trap	\xF3 = \x97
\x98	\x98 = trap	\xF2 = \x98
\x99	\x99 = trap	\xF4 = \x99
\x9A	\x9A = trap	\xF6 = \x9A
\x9B	\x9B = trap	\xF5 = \x9B
\x9C	\x9C = trap	\xFA = \x9C
\x9D	\x9D = trap	\xF9 = \x9D

Character code	Mapping from ISO Latin-1 to FrameMaker	Mapping from FrameMaker to ISO Latin-1
\x9E	\x9E = trap	\xFB = \x9E
\x9F	\x9F = trap	\xFC = \x9F
\xA0	\xA0 = trap	trap = \xA0
\xA1	\xA1 = \xC1	trap = \xA1
\xA2	\xA2 = \xA2	\xA2 = \xA2
\xA3	\xA3 = \xA3	\xA3 = \xA3
\xA4	\xA4 = \xDB	\xA7 = \xA4
\xA5	\xA5 = \xB4	\xB7 = \xA5
\xA6	\xA6 = \x7C	\xB6 = \xA6
\xA7	\xA7 = \xA4	\xDF = \xA7
\xA8	\xA8 = \xAC	\xAE = \xA8
\xA9	\xA9 = \xA9	\xA9 = \xA9
\xAA	\xAA = \xBB	trap = \xAA
\xAB	\xAB = \xC7	\xB4 = \xAB
\xAC	\xAC = \xC2	\xA8 = \xAC
\xAD	\xAD = \x2D	trap = \xAD
\xAE	\xAE = \xA8	\xC6 = \xAE
\xAF	\xAF = \xF8	\xD8 = \xAF
\xB0	\xB0 = \xFB	trap = \xB0
\xB1	\xB1 = trap	trap = \xB1
\xB2	\xB2 = trap	trap = \xB2
\xB3	\xB3 = trap	trap = \xB3
\xB4	\xB4 = \xAB	\xA5 = \xB4
\xB5	\xB5 = trap	trap = \xB5
\xB6	\xB6 = \xA6	trap = \xB6
\xB7	\xB7 = \xA5	trap = \xB7
\xB8	\xB8 = \xFC	trap = \xB8
\xB9	\xB9 = trap	trap = \xB9
\xBA	\xBA = \xBC	trap = \xBA
\xBB	\xBB = \xC8	\xAA = \xBB
\xBC	\xBC = trap	\xBA = \xBC
\xBD	\xBD = trap	trap = \xBD

Character code	Mapping from ISO Latin-1 to FrameMaker	Mapping from FrameMaker to ISO Latin-1
\xBE	\xBE = trap	\xE6 = \xBE
\xBF	\xBF = \xC0	\xF8 = \xBF
\xC0	\xC0 = \xCB	\xBF = \xC0
\xC1	\xC1 = \xE7	\xA1 = \xC1
\xC2	\xC2 = \xE5	\xAC = \xC2
\xC3	\xC3 = \xCC	trap = \xC3
\xC4	\xC4 = \x80	trap = \xC4
\xC5	\xC5 = \x81	trap = \xC5
\xC6	\xC6 = \xAE	trap = \xC6
\xC7	\xC7 = \x82	\xAB = \xC7
\xC8	\xC8 = \xE9	\xBB = \xC8
\xC9	\xC9 = \x83	trap = \xC9
\xCA	\xCA = \xE6	trap = \xCA
\xCB	\xCB = \xE8	\xC0 = \xCB
\xCC	\xCC = \xED	\xC3 = \xCC
\xCD	\xCD = \xEA	\xD5 = \xCD
\xCE	\xCE = \xEB	trap = \xCE
\xCF	\xCF = \xEC	trap = \xCF
\xD0	\xD0 = trap	\x2D = \xD0
\xD1	\xD1 = \x84	\x2D = \xD1
\xD2	\xD2 = \xF1	\x22 = \xD2
\xD3	\xD3 = \xEE	\x22 = \xD3
\xD4	\xD4 = \xEF	\x60 = \xD4
\xD5	\xD5 = \xCD	\x27 = \xD5
\xD6	\xD6 = \x85	trap = \xD6
\xD7	\xD7 = trap	trap = \xD7
\xD8	\xD8 = \xAF	\xFF = \xD8
\xD9	\xD9 = \xF4	trap = \xD9
\xDA	\xDA = \xF2	\x2F = \xDA
\xDB	\xDB = \xF3	\xA4 = \xDB
\xDC	\xDC = \x86	trap = \xDC
\xDD	\xDD = trap	trap = \xDD

Character code	Mapping from ISO Latin-1 to FrameMaker	Mapping from FrameMaker to ISO Latin-1
\xDE	\xDE = trap	trap = \xDE
\xDF	\xDF = \xA7	trap = \xDF
\xE0	\xE0 = \x88	trap = \xE0
\xE1	\xE1 = \x87	\xB7 = \xE1
\xE2	\xE2 = \x89	\x2C = \xE2
\xE3	\xE3 = \x8B	trap = \xE3
\xE4	\xE4 = \x8A	trap = \xE4
\xE5	\xE5 = \x8C	\xC2 = \xE5
\xE6	\xE6 = \xBE	\xCA = \xE6
\xE7	\xE7 = \x8D	\xC1 = \xE7
\xE8	\xE8 = \x8F	\xCB = \xE8
\xE9	\xE9 = \x8E	\xC8 = \xE9
\xEA	\xEA = \x90	\xCD = \xEA
\xEB	\xEB = \x91	\xCE = \xEB
\xEC	\xEC = \x93	\xCF = \xEC
\xED	\xED = \x92	\xCC = \xED
\xEE	\xEE = \x94	\xD3 = \xEE
\xEF	\xEF = \x95	\xD4 = \xEF
\xF0	\xF0 = trap	trap = \xF0
\xF1	\xF1 = \x96	\xD2 = \xF1
\xF2	\xF2 = \x98	\xDA = \xF2
\xF3	\xF3 = \x97	\xDB = \xF3
\xF4	\xF4 = \x99	\xD9 = \xF4
\xF5	\xF5 = \x9B	trap = \xF5
\xF6	\xF6 = \x9A	\x5E = \xF6
\xF7	\xF7 = trap	\x7E = \xF7
\xF8	\xF8 = \xBF	\xAF = \xF8
\xF9	\xF9 = \x9D	trap = \xF9
\xFA	\xFA = \x9C	trap = \xFA
\xFB	\xFB = \x9E	\xB0 = \xFB
\xFC	\xFC = \x9F	\xB8 = \xFC
\xFD	\xFD = trap	trap = \xFD

Character code	Mapping from ISO Latin-1 to FrameMaker	Mapping from FrameMaker to ISO Latin-1
<code>\xFE</code>	<code>\xFE = trap</code>	<code>trap = \xFE</code>
<code>\xFF</code>	<code>\xFF = \xD8</code>	<code>trap = \xFF</code>

Glossary

This glossary contains common terms used by FrameMaker, XML, and SGML. For references to more information about the terms, see the index.

ancestor	An element that contains a given element in a document's structure. For example, if a <code>Section</code> element contains a <code>Head</code> element followed by a <code>Paragraph</code> element, and the <code>Paragraph</code> contains a <code>Variable</code> element, the <code>Paragraph</code> and <code>Section</code> elements are both ancestors of the <code>Variable</code> element, but the <code>Head</code> element is not an ancestor of the <code>Variable</code> element. <i>See also</i> descendant, child element, parent element, and sibling.
API	Application Programming Interface. Enables developers to create API clients with other applications, such as databases, document management systems, CAD tools, and user interfaces, for automation, database publishing, HTML conversion and other purposes.
application definition	A data structure (and the associated files) describing part of a complete XML or SGML application assembled with FrameMaker. You store application definitions in the <code>structapps.fm</code> file.
attribute	A place to supply information about an element other than its hierarchical position and structure. An attribute value does not add content to a document.
attribute definition	The construct used to define a single attribute in a FrameMaker EDD or a DTD.
attribute definition list declaration	In markup, the declaration that provides the list of attribute definitions for one or more elements. Also called an ATTLIST. <i>See also</i> element declaration.
book	A grouping of FrameMaker documents that lets you work with them as a single unit. Lets you generate a single table of contents or other file from the documents, and simplifies printing, numbering, cross-referencing, and formatting.
CALS	Continuous Acquisition and Life Cycle Support. The US Department of Defense standard for the electronic delivery of documents.
catalog	A floating palette that stores predefined paragraph, character, or table formats.
CDATA	In markup, character data. In character data, no markup is recognized, other than the delimiters that end the character data. <i>See also</i> NDATA, #PCDATA, RCDATA, and SDATA.
child element	An element that is contained in a given element and that is one level below the given element. For example, if a <code>Section</code> element contains a <code>Head</code> element followed by a <code>Paragraph</code> element, and the <code>Paragraph</code> element contains a

	Variable element, the Head and Paragraph elements are both child elements of the Section element, but the Variable element is not. <i>See also</i> parent element, ancestor, descendant, and sibling.
concrete syntax	In SGML, a set of choices on the markup a document will use. Since SGML does not require any particular values for these choices, an SGML document requires a concrete syntax so a parser can correctly interpret it. <i>See also</i> reference concrete syntax.
container element	In FrameMaker, an element that can contain text, other elements, or both. Contrasts with certain specific element types—for example, a cross-reference element, which can contain nothing other than the cross-reference.
content model	In markup, the part of an element declaration that specifies both a model group and exceptions that define the allowed content of the element. Each markup element declaration has either a content model or declared content. <i>See also</i> content rules, declared content, general rule, and model group.
content rules	In FrameMaker, the part of an element declaration that specifies both the element's type and the kind of contents the element can have. <i>See also</i> format rules, content model, and general rule.
conversion table	In FrameMaker, a table associating parts of an unstructured document with their structured counterparts, used in converting an unstructured document to a structured document.
cross-reference	A passage in one place in a document that refers to another place, its cross-reference source, in the same or a different document.
cross-reference source	The place referred to by a cross-reference.
data	In markup, the characters of a document that represent the inherent information content. Such characters are not recognized as markup. <i>See also</i> markup.
data content notation	In markup, an application-specific interpretation of an element's data content, or of a data entity, that usually extends or differs from the normal meaning of the document character set. Frequently used to identify the format of an external entity containing a graphic.
declaration	In markup, markup that controls how other markup of a document is to be interpreted.
declared content	In an markup element declaration, specifies that the defined element's content is one of the reserved types CDATA, RCDATA, or EMPTY.
declared value	In an markup attribute definition, determines the type of attribute value, such as ID or NUTOKEN, that is valid when the attribute is specified. Although markup does not define the term <i>attribute type</i> , you can loosely think of an attribute's declared value as its type.

default value	In markup, the portion of an attribute definition that indicates whether an attribute is required and what value to use if the user does not specify one. In FrameMaker, refers only to the value to use if a user does not supply a value for an attribute.
delimiter	In markup, a character string used to identify a piece of markup or to distinguish markup from data. For example, > (greater-than sign) is the default closing delimiter for element tags.
descendant	Any element that is below a given element in a document's structure. For example, if a <code>Section</code> element contains a <code>Head</code> element followed by a <code>Paragraph</code> element, and the <code>Paragraph</code> element contains a <code>Variable</code> element, the <code>Variable</code> element is a descendant of both the <code>Paragraph</code> and the <code>Section</code> elements, but not of the <code>Head</code> element. <i>See also</i> ancestor, child element, parent element, and sibling.
DOCTYPE	In markup, the reserved name that follows the opening delimiter of a DTD. Informally used to refer to the document element.
document	A collection of information that is processed as a unit. A FrameMaker document is any file in FrameMaker format. A markup document includes an SGML declaration (for SGML), prologue, and document instance set.
document element	In markup, the highest-level element in a document. The generic identifier of this element is specified immediately after the <code>DOCTYPE</code> reserved name in the DTD.
document instance	In markup, the portion of a document that contains markup and data for a particular project such as a memo or book.
document type	A class of documents having similar characteristics, such as technical manual or internal memo.
document type declaration	In markup, a document type declaration (DTD) associates a document element with a set of declarations (the document type declaration subset).
document type declaration subset	In markup, a set of declarations determining such things as the markup to allow in a document and the elements and attributes for a document set. <i>See also</i> external DTD subset and internal DTD subset.
DTD	<i>See</i> document type declaration subset.
EDD	<i>See</i> element definition document.
element	A structural unit of a document. Holds and organizes the contents of the document.
Element Catalog	In FrameMaker, the information extracted from an EDD and stored within each structured FrameMaker document. Makes an external element definition document unnecessary. <i>See also</i> element definition document.

element declaration	In markup, information describing a particular element. Includes both a name (generic identifier) for the element and content rules. A markup document has an element declaration for each allowed element.
element definition	In FrameMaker, a set of rules describing an element. Includes a name (tag) for the element, content rules, and (optionally) context-sensitive format rules. A structured document has an element definition for each element allowed. <i>See also</i> content rules and format rules.
element definition document	A FrameMaker document that contains a set of element definitions for a class of documents. Can also include information on system defaults and on a structure application with which to associate this information. Also called an EDD.
element tag	In FrameMaker, the name assigned to an element and stored in the Element Catalog. <i>See also</i> generic identifier.
EMPTY	Keyword in an element definition indicating that the element cannot have content. In markup, <code>EMPTY</code> is a declared content.
end-tag	In markup, the markup that indicates the end of an element.
entity	In markup, a collection of characters that can be referenced as a unit. Used for many purposes in markup, such as graphics or frequently used sets of characters.
exclusion	An exception to the general rule or content model of an element. Specifies other elements that cannot appear anywhere in the element or in its descendants. Exclusions are not allowed in XML.
external cross-reference	In FrameMaker, a cross-reference to a source in a different file. Markup does not define this concept.
external DTD subset	In markup, an informal term for an external entity for which an external identifier appears at the beginning of a document type declaration and that is automatically referenced at the end of the document type declaration subset.
external entity	In markup, an entity that specifies an external object, such as a file.
facet	A pictorial representation of graphical data.
FDK client	In FrameMaker, any application created using the Frame Developer's Kit. <i>See also</i> Structure API client.
flow	<i>See</i> , "text flow."
format rules	In FrameMaker, the part of an element definition that specifies which predefined format to apply to an element. Format rules can use different formats for different contexts in a document. <i>See also</i> content rules.
general entity	In markup, an entity that can be referenced from within the content of an element or an attribute value literal.
general rule	In FrameMaker, a rule that specifies valid contents for an element and the order in which the contents can appear. Equivalent to the declared content of an

	element or the model group part of the content model of an element in markup. <i>See also</i> content rules.
generic identifier	In markup, the name identifying an element. <i>See also</i> element definition and element tag.
highest-level rule	In FrameMaker, a read/write rule that is not a subrule of another read/write rule.
HTML	Hypertext Markup Language. An encoding system used to describe the content and organization of an electronic document published on the World Wide Web.
ID attribute	An attribute of type <code>ID</code> , frequently used as an identifier to mark the source of a cross-reference. In a single document, a particular value for an <code>ID</code> attribute can be used only once.
IDREF attribute	An attribute whose value must be that of an <code>ID</code> attribute in the same markup document or FrameMaker document or book. Frequently used for cross-references.
impliable attribute	In markup, an attribute whose value does not have to be supplied. If a document does not supply a value, it is up to the processing software to correctly interpret the attribute. Such attributes use the default value <code>#IMPLIED</code> .
inclusion	An exception to the general rule or content model of an element. Specifies other elements that can appear anywhere in the element or in its descendants. Inclusions are not allowed in XML DTDs
invalid element	An element with contents that do not conform to content rules. May be missing required child elements, may not have a definition in the EDD or DTD, or may have text or child elements in a position not allowed by its content rules or by the exclusion and inclusion rules of its ancestors.
internal cross-reference	In FrameMaker, a cross-reference to a source in the same file.
internal DTD subset	In markup, an informal term for the declarations in a document type declaration that occur within brackets (<code>dso</code> and <code>dsc</code> delimiters) in the markup document entity, rather than being in an external entity.
internal entity	In markup, an entity whose replacement text is determined solely by information in its declaration.
ISO public entity	In SGML, an entity that occurs in one of the entity sets defined in Annex D of the SGML Standard. These entities provide commonly used special characters.
marker	In FrameMaker, a nonprinting character an end user inserts (such as an index entry) to indicate various types of information.
markup	Text added to the data of a document in order to convey information about it, such as hierarchical structure or formatting. This document also uses <i>markup</i> to generally refer to XML and SGML.

markup minimization	In SGML, any of various conventions for omitting markup in a document, including shortening or omitting tags and shortening entity references.
model group	In markup, an ordered list that specifies valid contents for an element (such as child elements) and the order in which the contents can appear. A model group is similar to a FrameMaker general rule.
NAMECASE parameter	In SGML, the part of the SGML declaration that determines case-sensitivity of markup.
NDATA	In SGML (and implicitly XML), non-SGML data. NDATA is data that needs special processing by the markup application. NDATA is typically used, for example, when representing graphics—in XML the graphic data would be non-parsed data. <i>See also</i> CDATA, #PCDATA, RCDATA, and SDATA.
parameter entity	In markup, an entity that can be referenced only within a DTD.
parent element	An element that contains a given element and is one level above it in the hierarchy. For example, if a <code>Section</code> element contains a <code>Head</code> element followed by a <code>Paragraph</code> element, the <code>Section</code> element is the parent element of the <code>Head</code> and <code>Paragraph</code> elements, but not of the <code>Variable</code> element. <i>See also</i> child element, ancestor, descendant, and sibling.
parser	<i>See</i> validating parser.
#PCDATA	In markup, parsed character data. This is normal text that can include markup to be parsed. Occurs in an markup element's model group and corresponds to <code><TEXT></code> in a FrameMaker element's general rule. <i>See also</i> CDATA, NDATA, RCDATA, and SDATA.
prefix	Text that is automatically placed before the content of an element. In FrameMaker, defined as part of the formatting of an element. For example, a <code>Quote</code> text range element might have an open quotation mark as its prefix and a close quotation mark as its suffix. <i>See also</i> suffix.
processing instruction	In an markup document, a way of indicating that the application needs to perform some special processing. For example, you can use a processing instruction to indicate a location in an markup document that should have a page break.
public identifier	In markup, a way of identifying an external entity. Formal public identifiers have a specified syntax that includes an identifier of the owner of the entity and an indication of the markup construct it provides. Formal public identifiers are typically available to any user of markup, not just the users at a particular company. Informal public identifiers may be available more widely than a single document or system, but perhaps no more widely than within a single company. <i>See also</i> system identifier

RCDATA	In markup, replaceable character data. In replaceable character data, no markup is recognized, other than character and entity references. RCDATA is valid only in SGML. <i>See also</i> CDATA, NDATA, #PCDATA, and SDATA.
read/write rule	In FrameMaker, interpreted commands you supply to modify how the software translates between FrameMaker and markup documents.
reference concrete syntax	In SGML, a particular concrete syntax defined by the SGML standard. <i>See also</i> concrete syntax.
reference page	An underlying page that stores repeatedly-used graphics and formatting information.
Rubi text	Small characters that appear above Japanese-language characters to indicate pronunciation.
rule	<i>See</i> SGML read/write rule.
SDATA	In SGML, specific character data. One common use is for specific characters that might not be in the standard character set. <i>See also</i> CDATA, NDATA, #PCDATA, and RCDATA.
SGML	An acronym for Standard Generalized Markup Language.
SGML application	Rules that apply SGML to a text processing application. Includes a formal specification of the markup constructs used in the application, expressed in SGML. Can also include non-SGML definitions of semantics, application, conventions, and processing.
SGML declaration	In SGML, the part of a document that tells a parser how to interpret markup in the document.
SGML read/write rule	<i>See</i> read/write rule.
sibling	Elements at the same level in the structure and with the same parent element. For example, if a <code>Section</code> element contains a <code>Head</code> element followed by a <code>Paragraph</code> element, the <code>Head</code> and <code>Paragraph</code> elements are siblings. <i>See also</i> ancestor, descendant, child element, and parent element.
source	<i>See</i> cross-reference source.
start-tag	In markup, the markup that indicates the beginning of an element.
Structure API client	In FrameMaker, an FDK client created to change the translation between FrameMaker and markup documents. <i>See also</i> FDK client.
subrule	In FrameMaker, an read/write rule that is part of another rule.
suffix	Text that is automatically placed after the content of an element. In FrameMaker, a prefix is defined as part of the formatting of an element. <i>See also</i> prefix.

system identifier	In markup, a way of identifying an external entity that's specific to the particular document or system. <i>See also</i> public identifier.
template	In FrameMaker, a document used to create new documents. A template can include all the formats, structure descriptions, and other information you need to create a document.
<TEXT>	In a FrameMaker element's general rule, indicates that the element can directly contain text characters and elements included by itself or its ancestors. <TEXT> corresponds to #PCDATA in a markup element's model group.
Text entity	An entity whose replacement text can contain both data and markup.
text flow	The text in a series of connected text frames. A text flow can also be contained in a single text frame, not connected to any other frame. A text flow with elements is a structured text flow.
text inset	Text imported by reference.
<TEXTONLY>	In a FrameMaker element's general rule, indicates that the element can directly contain text characters and cannot contain elements included by an ancestor. By default, on export <TEXTONLY> corresponds to a declared content of RCDATA in an SGML element's definition, or PCDATA in XML. On import FrameMaker translates declared content of RCDATA or CDATA to <TEXTONLY>.
valid document	A structured document that conforms to all its content rules. Every element in the document must be valid. In FrameMaker, every structured flow must have a highest-level element that is allowed at the highest level.
valid element	An element with contents that conform to its own content rules and to the inclusion and exclusion rules of all of its ancestors.
validating parser	In markup, a software module that parses the markup of an XML or SGML document and determines that the document structure conforms to a provided DTD.
variable	In FrameMaker, text that is defined once but can be used several times. Similar to some varieties of XML or SGML entity.
XML	An acronym for Extensible Markup Language. By definition, XML is a subset of SGML.
XSLT	An acronym for eXtensible Stylesheet Language: Transformations. It is a W3C language for transforming one XML document into another XML document. It can also transform an XML document into other text based formats including MIF

Index

- A**
 - abstract types Schema mapping 207
 - all element Schema mapping 200
 - ampersand (&)
 - in conversion tables 171
 - anchored frame (rule) 41
 - any element Schema mapping 204
 - anyType Schema mapping 196
 - application definition files ??–30
 - contents of 9
 - default information 11
 - defining applications in 9
 - document elements 13
 - DTDs for import and export 14
 - entity catalogs 15–16
 - external entities 17–18
 - filename extensions, specifying 21
 - files for rules documents 22
 - individual entities 16
 - length of log files 30
 - namespaces, enabling 22
 - public identifiers 18
 - read/write rules documents 22
 - search path for external entities 19–20
 - SGML declarations 24
 - structure API clients 27
 - templates for import 26
 - application files
 - managing CSS 24
 - Schema, specifying 23
 - XSL transformation, specifying 25
 - asterisk (*)
 - in conversion tables 171
 - attribute (rule) 44
 - attributes
 - defaults in Schema 204
 - for identifying overrides 176
 - in conversion tables 173
 - mapping of Schema to DTD 201
 - attributes, read/write rules for 32
 - attribute 44
 - drop 51
 - fm attribute 74
 - fm element 75
 - implied value is 92
 - is fm attribute 100
 - is fm property 112
 - is fm property value 119
 - is fm value 131
 - value 157
- B**
 - books, read/write rules for 33
 - generate book 89
 - output book processing instructions 139
 - put element 89
 - use processing instructions 89
- C**
 - CALS table model 209–214
 - attribute structure 213
 - colspec elements 212, 213
 - element and attribute declarations 210
 - element structure 212
 - spanspec elements 212, 213
 - CALS tables
 - read/write rules for 215–217
 - character formats
 - wrapping text formatted without 176
 - character map (rule) 47
 - character set mapping 231–237
 - characters allowed
 - in conversion tables 168
 - choice element Schema mapping 199
 - comma (,)
 - in conversion tables 171
 - complex type Schema mapping 198, 205
 - named 200
 - conversion tables 163–179
 - adding rules to 167–174
 - attributes in 173
 - building tables from format tags with 178
 - columns and rows in 163, 167
 - documents for holding 164
 - flagging format overrides with 176
 - format and element tags in 165, 167, 169
 - generating initial 165
 - nesting graphics or tables with 177
 - object type identifiers in 169
 - order of rules in 164
 - promoting graphics or tables with 175

- qualifiers for element tags in 167, 173
- root element 168
- setting up from scratch 166
- testing and correcting 178
- updating 166
- wrapping elements with 170
- wrapping objects with 169
- wrapping sequences with 171
- wrapping untagged text with 176

cross-references, read/write rules for 33

- fm element unwrap 75
- fm property 78
- is fm cross-reference element 105
- is fm property 112
- is fm property value 119
- is fm value 131
- value is 78

CSS

- managing generation 24

CSS files 29

CSS import 25

D

- default
 - SGML declaration 219–221
- defaults
 - mapping of Schema to DTD 204
- DOCTYPE elements 13
- document type declarations (DTDs)
 - specifying location of 14
- drop (rule) 51
- drop content (rule) 53
- DTD 196

E

- element (rule) 54
- element tags
 - in conversion tables 165, 167, 169
- elements
 - defaults in Schema 204
 - mapping of Schema to DTD 202
- elements, read/write rules for all 31
 - attribute 44
 - drop 51
 - drop content 53
 - element 54
 - fm element 75
 - is fm element 106
 - preserve fm element definition 140, 141
 - unwrap 154

- encoding 29
 - of CSS files 29
- end vertical straddle (rule) 57
- entities
 - external files for 17–18
 - ISO public 223–230
 - searching for external files 19
 - searching for filename patterns 17
 - specifying location of 16
 - specifying search path for 19–20
- entities, read/write rules for 34
 - drop 51
 - entity 59
 - entity name is 61
 - external data entity reference 69
 - is fm char 103
 - is fm reference element 121
 - is fm variable 133
 - reformat as plain text 146
 - reformat using target document catalogs 147
 - retain source document formatting 148
- entity (rule) 59
- entity catalogs
 - format of entries in 15
 - searching for 16
 - specifying location of 15–16
 - uses for 15
- entity name is (rule) 61
- equation (rule) 63
- equations
 - in conversion tables 170
- equations, read/write rules for 34
 - entity name is 61
 - equation 63
 - export dpi 64
 - export to file 67
 - fm property 78
 - is fm equation element 107
 - is fm property 112
 - is fm property value 119
 - is fm value 131
 - notation is 137
 - specify size in 149
 - value 157
 - value is 78
- export dpi (rule) 64
- export to file (rule) 67
- exporting XML
 - XSL transformation 26
- external data entity reference (rule) 69
- external dtd (rule) 70

F

- facet (rule) 72
- fm attribute (rule) 74
- fm element (rule) 75
- fm element unwrap (rule) 75
- fm marker (rule) 76
- fm property (rule) 78
- fm variable (rule) 87
- fm version (rule) 89
- footnotes
 - in conversion tables 170
- footnotes, read/write rules for 35
 - is fm footnote element 108
- format overrides, flagging in conversion tables 176
- format tags
 - in conversion tables 165, 167, 169

G

- generate book (rule) 89
- graphics
 - nesting in conversion tables 177
 - promoting in conversion tables 175
- graphics, read/write rules for 35
 - anchored frame 41
 - entity name is 61
 - export dpi 64
 - export to file 67
 - facet 72
 - fm property 78
 - is fm graphic element 109
 - is fm property 112
 - is fm property value 119
 - is fm value 131
 - notation is 137
 - specify size in 149
 - value 157
 - value is 78
- group element Schema mapping 198

I

- impact of stylesheet element 25
- implied value is (rule) 92
- import
 - Schema mapping 205
- importing XML
 - XSL transformation 26
- include
 - Schema mapping 205
- include dtd (rule) 94
- include sgml declaration (rule) 96

- initial conversion tables 165
- insert table part element (rule) 97
- is fm attribute (rule) 100
- is fm char (rule) 103
- is fm cross-reference element (rule) 105
- is fm element (rule) 106
- is fm equation element (rule) 107
- is fm footnote element (rule) 108
- is fm graphic element (rule) 109
- is fm marker element (rule) 111
- is fm property (rule) 112
- is fm property value (rule) 119
- is fm reference element (rule) 121
- is fm rubi element (rule) 123
- is fm rubi group element (rule) 124
- is fm system variable element (rule) 125
- is fm table element (rule) 126
- is fm table part element (rule) 128
- is fm value (rule) 131
- is fm variable (rule) 133
- is processing instruction (rule) 134
- ISO Latin-1 character set 231–237
- ISO public entities 223–230
 - declarations and rules 228–230
 - default character formats 227
 - default variable definitions 227
 - entity declaration files 225
 - entity read/write rules files 225
 - format of entity rules 226

K

- key element Schema mapping 207

L

- line break (rule) 134
- log files
 - limiting length of 30

M

- mapping of Schema elements 196
- marker text is (rule) 136
- markers, read/write rules for 36
 - drop 51
 - external data entity reference 69
 - fm marker 76
 - fm property 78
 - is fm marker element 111
 - is fm property 112
 - is fm property value 119

- is fm value 131
- is processing instruction 134
- marker text is 136
- processing instruction 143
- value 157
- value is 78

markup language documents, read/write rules for 37

- external dtd 70
- include dtd 94
- write structured document instance only 159

markup languages, translation to and from

- cross-references ??–21

N

- named attribute group Schema mapping 201
- named complex type Schema mapping 200
- namespaces
 - and Schema 195
 - extra attributes from Schema mapping 196
- notation is (rule) 137

O

- object type identifiers, in conversion tables 169
- output book processing instructions (rule) 139

P

- paragraph formats
 - building table structure from 178
- parentheses
 - in conversion tables 171
- plus sign (+)
 - in conversion tables 171
- PostProcessing element 26
- PreProcessing element 26
- preserve fm element definition (rule) 140, 141
- processing instruction (rule) 143
- processing instructions (PIs), read/write rules for 37
 - drop 51
 - fm marker 76
 - is processing instruction 134
 - output book processing instructions 139
 - processing instruction 143
 - use processing instructions 89
- PROMOTE keyword 175
- proportional width resolution is (rule) 144
- public identifiers 18
- put element (rule) 89

Q

- qualifiers, in conversion tables 163, 167, 173
- question mark (?)
 - in conversion tables 171
- quotation marks ("), in attribute values 173

R

- read/write rules
 - documents for 22
 - for CALS tables 215–217
 - including files with 22
 - summary of 31–39
- reader (rule) 145
- redefine Schema mapping 205
- reformat as plain text (rule) 146
- reformat using target document catalogs (rule) 147
- retain source document formatting (rule) 148
- root element 168
- Rubi groups, read/write rules for
 - is fm rubi element 123
 - is fm rubi group element 124

S

- Schema
 - and namespaces 195
 - extra namespace attributes 196
 - mapping to DTD 196
 - mixed content models 203
 - specifying file location 195
 - structure application element 23
 - types not mapped 207
- sequence element Schema mapping 198
- SGML
 - defining an application 9
 - optional unsupported features 222
- SGML declarations
 - default for FrameMaker 219–221
 - specifying location of 24
- SGML documents, read/write rules for
 - include sgml declaration 96
- SGML parser
 - concrete syntax variants 221
- simple type Schema mapping 196
- specify size in (rule) 149
- start new row (rule) 151
- start vertical straddle (rule) 152
- structure API clients
 - specifying location of 27
- structure applications
 - defining 9

structure, adding to documents. *See* conversion tables
stylesheet element
 impact on CSS import feature 25
stylesheets
 XSL 25
system variables
 in conversion tables 170

T

table ruling style is (rule) 153
tables
 building structure from format tags 178
 CALS attribute usage 209
 nesting in conversion tables 177
 promoting in conversion tables 175
tables, read/write rules for 38
 end vertical straddle 57
 fm property 78
 insert table part element 97
 is fm property 112
 is fm property value 119
 is fm table element 126
 is fm table part element 128
 is fm value 131
 proportional width resolution is 144
 start new row 151
 start vertical straddle 152
 table ruling style is 153
 use proportional widths 156
 value 157
 value is 78
templates
 specifying location of 26
text insets, read/write rules for 39
 entity 59
 reformat as plain text 146
 reformat using target document catalogs 147
 retain source document formatting 148
text, read/write rules for
 character map 47
 entity 59
 is fm char 103
 line break 134

U

unique element Schema mapping 207
untagged formatted text, wrapping 176
unwrap (rule) 154
use processing instructions (rule) 89
use proportional widths (rule) 156

user variables
 in conversion tables 170

V

value (rule) 157
value is (rule) 78
variables, read/write rules for 39
 drop 51
 entity 59
 fm element unwrap 75
 fm variable 87
 is fm system variable element 125
 is fm variable 133
vertical bar (|)
 in conversion tables 171

W

wildcard characters
 in conversion tables 168
wrapping with conversion tables
 document objects 169
 elements 170
 sequences of elements or paragraphs 171
 untagged formatted text 176
write structured document instance only (rule) 159
writer (rule) 160

X

XML
 defining an application 9
 specifying Schema location 195
 using CSS stylesheets 24
 XSL transformations 25
XML Schema, *See* Schema
XSL files
 associating with XML applications 25
XSL transformation (XSLT) 25
